



Agile Business Suite

Installation and Configuration Guide

Release 8.0.1039

May 2025

3826 5815-010

NO WARRANTIES OF ANY NATURE ARE EXTENDED BY THIS DOCUMENT. Any product or related information described herein is only furnished pursuant and subject to the terms and conditions of a duly executed agreement to purchase or lease equipment or to license software. The only warranties made by Unisys, if any, with respect to the products described in this document are set forth in such agreement. Unisys cannot accept any financial or other responsibility that may be the result of your use of the information in this document or software material, including direct, special, or consequential damages.

You should be very careful to ensure that the use of this information and/or software material complies with the laws, rules, and regulations of the jurisdictions with respect to which it is used.

The information contained herein is subject to change without notice. Revisions may be issued to advise of such changes and/or additions.

Notice to U.S. Government End Users: This software and any accompanying documentation are commercial items which have been developed entirely at private expense. They are delivered and licensed as commercial computer software and commercial computer software documentation within the meaning of the applicable acquisition regulations. Use, reproduction, or disclosure by the Government is subject to the terms of Unisys' standard commercial license for the products, and where applicable, the restricted/limited rights provisions of the contract data rights clauses.

Contents

Section 1. Introduction

Section 2. Agile Business Suite Overview

About Agile Business Suite	2-1
Preparing for Installation of Agile Business Suite	2-1
SQL Server Configuration	2-3
AB Ready Tool	2-4
Installing Agile Business Suite Developer	2-6
Installing Client Environment Software	2-6
Installing Source Control	2-9
Installing Agile Business Suite Runtime	2-9
Windows Compatibility	2-9
Installation Problem Reporting	2-10
Installing Agile Business Suite in a Distributed Runtime Configuration	2-11
Configuring Users and Network Communications	2-12
Installing Visual Studio	2-13
Installing Agile Business Suite Runtime	2-14
Installing Agile Business Suite DB Migrate Utilities	2-14
Installing Agile Business Suite Developer	2-14
Installing SQL Server 2019	2-14
Distributing Configuration Files	2-15
Configuring for Distributed Deployment	2-16

Section 3. Developer Installation

Required Software Configuration	3-1
Required Agile Business Suite Software	3-4
Installation of Visual Studio 2019	3-4
Minimum Hardware Requirements	3-5
Workstations	3-5
For the Model Database	3-6
Preparing Your Network for Developer	3-7
Access Rights to Drives, Directories, and Files	3-7
Installing Developer on a Workstation	3-7
Prerequisites	3-7
Performing the Developer Installation	3-8

Silent Installation.	3-15
Installing Developer with Windows Remote Desktop Services	3-16
What are Remote Desktop Services?	3-16
Recommended Configuration	3-17
Requirements for a Remote Desktop Services	
Installation	3-17
Installation Procedure	3-17
Known Issues with Developer on Windows Remote	
Desktop Services	3-20
Verifying Your Installation.	3-20
Creating an AB Suite Test Project.	3-21
Creating an AB Suite Client Framework Test Project	3-25
Verifying and Viewing Online Help	3-27
Uninstalling the AB Suite Developer.	3-29
Silent Uninstallation	3-30
Uninstalling and Reinstalling AB Suite	3-31
Backing up and Restoring	3-31
Using AB Suite COM+ Migrator Utility.	3-32
Backup AB Suite Runtime COM+ Application Settings . .	3-33
Restore AB Suite Runtime COM+ Application Settings . .	3-34
Backup AB Suite Generated Application Settings	3-35
Restore AB Suite Generated Application Settings	3-36
Using Command Line Options	3-37
Enabling LargeAddressAware option for Agile Business Suite in	
Windows	3-39

Section 4. Developer Configuration

Configure Debugger for Normal Users.	4-1
File Permissions for Builder Output and Cache	
Directories	4-1
File Permissions for Existing Data Folder	4-1
Adding New Non-administrative User Access to	
Debugger.	4-2
Changing Builder Output and Cache Directories	4-3
Database Permissions Needed	4-3
Configure Debugger for Remote Desktop Users.	4-4

Section 5. Client Environment Installation

Required System Software	5-1
Generation Workstation	5-1
Client Workstation	5-2
Minimum Hardware Requirements	5-5
Installing the Client Environment	5-6

Installing Winform	5-6
Configuring Winform	5-7
Configuring Winform for Cloned Reports	5-9
Installing Component Enabler	5-10
Custom Setup	5-11
Component Enabler for Java	5-12
CE Generate for .NET Framework	5-12
CE Runtime for .NET Framework	5-16
Generator Customization Kit	5-17
Completing the installation	5-17
Oracle JRE Installation and Configuration	5-17
OpenJDK Installation.	5-22
Installing the Presentation Client	5-22
Standalone Installation for Windows Operating Systems.	5-25
Standalone Installation for non-Windows Operating Systems.	5-25
Using the Redirector	5-26
Using Component Enabler with Browsers	5-27
Using Component Enabler with COM Based Applications	5-27
Customizing the Presentation Client Installation	5-27
Presentation Client Silent Installation	5-28
Installing Business Integrator.	5-33
Installing Client Framework	5-34
Installing Windows TLS Certificate	5-35
Change, Repair, or Uninstall Agile Business Suite Client Environment.	5-36

Section 6. Runtime for Windows® Operating System Installation

Required System Software Configuration.	6-1
Minimum Hardware Requirements	6-3
Installing Runtime for Windows.	6-4
COM+ Network Access in Windows 11 and Windows Server 2019 / 2022	6-4
Setting up User Accounts	6-5
Unisys Installation Interface.	6-5
Custom	6-6
Completing the Installation	6-7
Silent Installation	6-8
Uninstall Agile Business Suite Runtime	6-9

Section 7. Runtime for Windows® Operating System Configuration

Configuring User Accounts	7-1
The Application User.	7-1
The Application Administrative User.	7-3
Changing Passwords	7-6
Changing Accounts.	7-6
Change Database User Password	7-7
Server Configuration	7-8
SQL Server.	7-8
Runtime Server Configuration	7-8
User Profile Service Configuration	7-9
User Configuration	7-10
Client Users	7-10
Administrative User	7-10
Configuring Runtime for Normal users.	7-13
Adding New Non-administrative User to Access Runtime.	7-13
Securing the Runtime Administration Tasks	7-13
Configuring Secure RATL.	7-14
Adding Registry Keys for TLS 1.3.	7-15
Other Security Considerations	7-15
Protecting Your Network Traffic.	7-15
Deployment	7-15
Debugger.	7-15
Runtime Setup	7-16
Clustering AB Suite Runtime	7-16
Nodes	7-16
Virtual IP Address/Network Name	7-16
Resources	7-17
Dependencies	7-17
AB Suite Application and Database Layers	7-17
Cluster Resource Group Setup.	7-17
AB Suite Runtime Software Installation in a Cluster	7-18
Installing AB Suite Runtime	7-18
Configuring AB Suite Protocol Adaptor Resources	7-18
Defining a Generic Script Resource	7-19
Setting up Dependencies	7-19
Adding a Runtime Server.	7-20
Adding a Database Server Registration.	7-20
Adding a Database	7-20
Installing the Report Output Control System.	7-22
Database Configuration	7-23
Detaching a Database	7-23
Deleting a Database	7-23

Section 8. Runtime for ClearPath MCP Installation and Configuration

Pre-Installation Requirements	8-1
Products and Terminology	8-1
Required System Software Requirements	8-2
Minimum Hardware Requirements	8-5
Setting Up the Host	8-6
Configuring Terminal Devices for Runtime for ClearPath MCP.	8-6
Installing and Configuring Runtime for ClearPath MCP	8-10
Preparing for Installation	8-10
Installation Checklist	8-10
General Notes About Installation	8-11
Copying the Runtime Install Job from the Release Media	8-13
Installing the MCP Runtime Software	8-13
UVMS: Setting up for Failover in a High Availability Environment.	8-20
Configuring COMS for Applications	8-21
Installing and Configuring the Remote Access Server (RAS)	8-23
Installing and Configuring Remote Subroutine Server . . .	8-47
Setting up FTP	8-49
Deploying the First Application After Installing Runtime.	8-51
Deploying the System with Minimal Downtime	8-52
Deploying the System without Delaying the Deployment	8-54
Updating the System with MCP Runtime Transfer	8-55
Migrating to Release 8.0	8-57
Migration Procedure	8-57
Using Dell Storage Replication Capabilities	8-57
Planned Recovery	8-58
Online Application Takeover.	8-58
Report Recovery During Unplanned Takeover	8-60
Configuring a Secure Client to APPL BLD Connection	8-61

Section 9. Runtime for ClearPath OS 2200 Installation and Configuration

Pre-installation Requirements	9-1
About Agile Business Suite Software.	9-1
Hardware Requirements	9-2
System Software Requirements	9-3
Other Software Considerations	9-6
Installing and Configuring the Required OS 2200 System Software	9-7

Configuring and Regenerating EXEC	9-7
CPCOMM and MCB Configuration	9-11
UDS Software Configuration	9-12
Installing AB Suite Runtime for ClearPath OS 2200	9-13
Installation Procedure	9-13
COMUS Build Procedure	9-14
Registering the Release Tape with COMUS	9-14
Changing the Default Configuration Parameters	9-15
Building the Runtime	9-16
Installing Runtime	9-18
About Runtime Release Tape	9-18
Installing with SOLAR	9-18
Installation Modes for Setting Up the HUBs	9-21
Installation Modes for Builder Server	9-22
Installing Runtime with the XTC	9-24
About Shared and Local Application Groups	9-24
Installing Runtime on a Shared Application Group	9-25
Installing Runtime with PAEXEC	9-26
Before Using Runtime	9-26
Starting Background Runs	9-27
Reinstalling Runtime	9-27
Installing Additional Copies of Runtime	9-29
Uninstalling Runtime	9-30
COMUS Configuration and SOLAR Installation Parameters	9-31
COMUS Configuration Main Menu	9-31
General Configuration Parameter Screens	9-32
General Configuration Parameter Screen 1	9-32
General Configuration Parameter Screen 2	9-34
General Configuration Parameter Screen 3	9-35
Processor File Names Screen	9-38
Processor File Names Screen 1	9-38
Processor File Names Screen 2	9-40
Common Bank Attributes Screen	9-41
HUB Configuration Parameters Screens	9-42
HUB Configuration Parameter Screen 1	9-42
HUB Configuration Parameter Screen 2	9-43
OLTP Configuration Parameters Screen	9-45
LRSS Configuration Parameters Screen	9-45
DG (Builder Server) Configuration Parameters Screen	9-46
COMUS Run Parameters	9-47
Files Created by Agile Business Suite	9-49
Files Created when Installing Runtime	9-49
Files Created when Configuring and Generating a System	9-51

Appendix A. Installing Interim Corrections

Installing Interim Corrections for Runtime for ClearPath MCP	A-2
Copying the Runtime Install Job from the Release Media	A-2
Installing the Authenticate File	A-2
Installing the MCP Runtime Software	A-3
Performing the First Application Build after Updating the Runtime.	A-4
Application Build Instructions	A-4
LINCSUPPORT.	A-4
ENVIRONMENT, LSS, and COMS_LINC_TP.	A-5
LOGIC.	A-6
REPORT_INFO.	A-6

Appendix B. Creating and Configuring User Accounts Using the AB Ready Tool

Configuring Existing AB Suite Service Accounts.	B-2
Creating and Configuring New AB Suite Service Accounts Manually	B-3
Creating and Configuring New AB Suite Service Accounts Automatically	B-6

Section 1

Introduction

About This Guide

This document is a guide for installing and configuring Agile Business Suite 8.0 in a standalone or network environment.

Audience

This document is primarily for those who install Agile Business Suite 8.0 either on a single workstation or on a network. It is also useful for system administrators and new users of Agile Business Suite 8.0.

Documentation Update

This document contains all the information that was available at the time of publication. Changes identified after the release of this document are included in the [Information Center](#).

Note: *If you are not logged into the Product Support site, you are asked to do so.*

What's New in this Release

The following table lists the changes made to the document in this release:

Topic	Description
Using Dell Storage Replication Capabilities	Added the Using Dell Storage Replication Capabilities section
AB Ready Tool	Added information on Checking Prerequisites Using the AB Ready Tool
Required Software Configuration	Added information on Checking Prerequisites for Developer Using the AB Ready Tool
Installing Component Enabler	Added information on Checking Prerequisites for Component Enabler Using the AB Ready Tool

Introduction

Topic	Description
Installing the Presentation Client	Added information on Checking Prerequisites for Presentation Client Using the AB Ready Tool
Required System Software Configuration	Added information on Checking Prerequisites for Windows Runtime Using the AB Ready Tool
Configuring Existing AB Suite Service Accounts	Added Appendix on Creating and Configuring User Accounts Using the AB Ready Tool

Section 2

Agile Business Suite Overview

This section provides an overview of the installation of the Agile Business Suite software.

About Agile Business Suite

Agile Business Suite is an enterprise wide application development and deployment environment for Windows® workstations. Agile Business Suite integrates into a single environment that facilitates to design, develop, test, and deploy systems, in either single user or multiuser modes. The default installation provides for multiuser operation automatically. Agile Business Suite also includes the runtime system for the deployed application.

Preparing for Installation of Agile Business Suite

Agile Business Suite 8.0 prompts you with systems or software pre-requisite dialog box to confirm if all the required software has been installed before installing Agile Business Suite 8.0.

Prior to the installation of Agile Business Suite Developer or Agile Business Suite Runtime, an administrator must set up two accounts:

- Application User
- Application Administrative User

An administrator is allowed to specify which user accounts are used to represent both, the Application User and the Application Administrative User.

Refer to Creating the User Accounts or [Section 3, Developer Installation](#).

It is recommended that for optimal security the accounts are not granted any rights or privileges over and above the minimum required privileges by Agile Business Suite to perform the necessary tasks. If you are installing Agile Business Suite Runtime on a machine which already has an installation of Agile Business Suite Developer operating, you do not need to create a second set of users.

If you wish to have the model database and runtime environment on a server, to which development workstations will connect in a multiuser system and provide debugging functionality, you should carry out these preparation and installation steps for each workstation.

Note: *It is not possible to run the setup.executable from a mapped drive using Remote Desktop. For example, you cannot access machine C, which is mapped to machine B, through Remote Desktop which is using machine A. However, you can access setup.exe from machine B so long it is not mapped and uses UNC path instead.*

The identity of an Application User is assumed by those Agile Business Suite applications that deal with the normal every day operations. The identity of an Application Administrative User is assumed by those Agile Business Suite applications that are required to perform administrative tasks, which require a higher privilege level. Thus, the likelihood of an elevation of privilege attack is minimized as the Application User, whose identity is assumed by most Agile Business Suite applications that are accessible by normal Agile Business Suite users, is a low privileged account. Those Agile Business Suite applications that are required to run under the identity of an Application Administrative User are properly secured so that normal Agile Business Suite users cannot access them, and therefore cannot launch elevation of privilege attacks.

It is not recommended that the Application Administrative User account should ever be changed after it is initially setup prior to installation. If the account needs changing for security reasons, whether the account is simply renamed or if it is completely deleted and a new account created in its place, the administrator needs to manually replace all references to the old account with the new one.

Creating the User Accounts

To create the Application User, perform the following:

1. Open Computer Management, accessible from the Administrative Tools folder in the Control Panel.
2. From the Tree view, expand System Tools\Local Users and Groups.
3. In the Users folder, right-click and select **New User** to create a user to represent the Application User. You may refer to the user by any name, however neither the name nor password should contain spaces.
4. In the **New User** dialog box:
 - Clear the **User must change password at next logon** check box.
 - Select the **Password never expires** check box.

After you have created the Application User, repeat the steps above to create a User to represent the Application Administrative User.

Note: *Once you have created the Application Administrative User, you must add that user to the Administrators group. Only the application administrator account name should be added to the administrators group. The application user account name should NOT be added to the administrators group.*

Configuring the User Accounts

It is important that these user accounts have certain User Rights. These User Rights may already exist for the users, if they have been added to a pre-existing group. If the users do not already possess the User Rights by association with an existing group, they should be configured as follows.

To configure both users, perform the following:

1. Open Local Security Policy, accessible from the Administrative Tools folder in the Control Panel.
2. In the Tree view, expand the Local Policies/User Rights Assignment.
3. Assign the following User Rights to the Application Administrative User:
 - Access this computer from the network
 - Act as part of the operating system
 - Log on as a batch job
 - Replace a process level token
4. Assign the following User Rights to just the Application User:
 - Access this computer from the network
 - Log on as a batch job
 - Log on as a service
5. Close the Local Security Policy dialog box.

Both user accounts are primarily required for the runtime functionality of the Agile Business Suite software, some of which is used for the debugging mechanism in Developer.

These user accounts are created for application purposes only. Do not log in using these account names. Log in using your own login credentials.

SQL Server Configuration

The SQL Server must be configured to allow both SQL Server and Windows authentication.

The Application User must be granted a SQL Server login to the database server that is to be used by Agile Business Suite. The login is case-sensitive and must be in the same case as specified in the Windows Security Accounts Manager database.

Configuring the Default 'sa' Account

When SQL Server is installed, by default the 'sa' account is created with a blank password. In order to ensure that unauthorized users do not gain access to your server, it is recommended that you assign a password to the 'sa' account. If a password is not assigned and an unauthorized user gains access using the 'sa' account, they have full control of all databases contained on your server.

Configuring SQL Server for Remote Access

To enable remote access to your model databases, perform the following:

1. In SQL Server Configuration Manager, navigate to **SQL Server Network Configuration > Protocols for MSSQLSERVER**, enable the following protocols for the SQL Server instance hosting the model databases:
 - Named Pipes
 - TCP/IP
2. In SQL Server Management Studio, give model users permission to access your model databases – you can grant access to users individually or as Windows Groups.


Refer to the *Microsoft SQL Server documentation* for more information on configuring SQL Server.

AB Ready Tool


You can run the AB Ready tool to check if the prerequisite software for the AB Suite components is present in the computer where you are planning to install AB Suite.

To run the AB Ready tool and check for the prerequisite software:

1. In the AB Suite installer folder, navigate to **CD Developer\ABReady**.
2. Run the **AB Ready Tool** application.
3. In the **Welcome to AB Ready Tool** screen, select **Check for Prerequisites**.



4. In the **Check For Prerequisites** screen, select the **AB Suite: Component** and click **Check**.



The prerequisite software status for the selected component is displayed.

Installing Agile Business Suite Developer

The Agile Business Suite Developer can be installed standalone on a workstation, or as a network installation with shared components. All installation types are detailed in this document.

Note: *The user performing the installation must be a Domain user, if the Application user and Application Administration user are domain accounts and the user also needs to be a member of the same domain as the Application User and Application Administration User accounts, or a member of a trusted domain.*

When you are installing Developer, it appears as the following software modules:

Module	Description
Developer	Developer consists of System Modeler, which includes a logic editor, logic validation, screen painter, debugger, and version control utilities. All development data is stored in the Model database. Developer also includes the Model Importer and Exporter which allows you to load an existing LCIF file into your model database or export the model database.
Builders	Integrates with Visual Studio.NET and enables you to generate and deploy a Runtime system for a target host directly from your Development environment.

Installing Client Environment Software

The following optional software is available for testing, viewing, and operating your Agile Business Suite system at Runtime.

You can use these products to web-enable and provide remote access to a Runtime system. When you are installing the Client Tools Environment, it appears as the following software modules.

Module	Description
Windows Forms	The Winform standalone installation comes in two versions Winform (32-bit) – A 32-bit application that is used to display painted forms on the screen for user interaction and can be used with Debugger. Winform (64-bit) – A 64-bit application that is used to display painted forms on the screen for user interaction.

Module	Description
Component Enabler	An environment for opening Agile Business Suite applications to current Web technology and enterprise systems running Windows operating systems. Component Enabler provides standard component interfaces to remote applications, opening them up to modern client tools and applications.
Presentation Client	Presentation Client displays GUI objects created in Developer Painter true to the way in which they were designed and to offer the functionality needed to provide an interface to remote host systems.
Business Integrator	Business Integrator provides a set of tools to assist you in developing and extending your Agile Business Suite systems to provide electronic business capability.

Module	Description
Client Framework	The Client Framework standalone installation comes in two versions Client Framework (32-bit) – A 32-bit version that supports client applications running on a 32-bit operating system. Client Framework (64-bit) – A 64-bit version that supports client applications running on a 64-bit operating system. The contents and capabilities of both versions are the same. The only difference is that each version installs the appropriate assemblies required to communicate with the runtime system from either a 32-bit or 64-bit client application. Both packages (32-bit and 64-bit) install the following components: • Windows Presentation Foundation (WPF) Client – This allows you to install the WPF Client on end-user machines that do not have AB Suite Developer. The WPF Client allows you to run Client Framework applications developed by using the WPF/XAML technology inside a WPF Container supplied and supported by Unisys. The WPF Client installation also includes the assemblies required to connect to an AB Suite runtime system. • Client Framework MVC Scaffolder Extension – This allows you to scaffold MVC Views from a set of DataModels generated by the AB Suite application. • Client Framework NuGet Packages – Direct Connect Assemblies – Use this to install and reference the Access Layer API assemblies for connecting directly to the runtime system by using COM/DCOM. – Remote Connect Assemblies – Use this to install and reference the Access Layer API assemblies for connecting to the runtime system by using the WCF Gateway. – WPF Toolkit for Client Framework – Use this to install the Toolkit assemblies for developing WPF Client applications. Notes: • <i>The MVC Scaffolder and the NuGet Packages require Visual Studio 2019.</i> • <i>This software must not be installed on a machine with AB Suite Developer already installed, as the AB Suite Developer installation will have the same components already installed. The Client Framework Standalone installation is intended for use on machines that do not have the AB Suite Developer available.</i>

You can install the Client Environment Software from the Unisys Installation Interface.

Installing Source Control

In AB Suite, you can use source control client to compare two models or a model with a set of files in a directory. Azure DevOps allows you to effectively manage software development projects. Azure DevOps enables multiple project objectives including source code storage, checkins and conflict resolution, and bug and issue tracking.

Refer to the Azure documentation in the *Visual Studio Online Help* for more information on minimum software and hardware configurations.

Installing Agile Business Suite Runtime

Agile Business Suite Runtime can be installed on any workstation from the AB Suite Runtime installer or as a network installation with shared components. All installation types are detailed in this document. The installation details vary depending on the host platform on which you are installing runtime.

AB Suite 8.0 Runtime is a 64-bit application and is not supported in a Native 32-bit environment. When you try to install runtime in a 32-bit environment, the error message “This installation package is not supported by this processor type. Contact your product vendor” appears.

The ExternalClassHost32 COM+ application includes the legacy 32-bit components required to host 32-bit external classes and LETSJ_SJIS conversion.

As the internal code mappings of the Japanese character set are different for the LETS-J code (on OS 2200) and the Shift JIS code (on Windows), a set of translation libraries specific to the encoding used for EAE OS 2200 is required. These libraries are the same as those used by EAE Developer. When using external classes targeting Kanji data, you must place the following libraries in the path specified by the ProductDir32 registry key, HKEY_LOCAL_MACHINE > Software > Wow6432Node > Unisys > ABSuite > (version) > SM Runtime; for example, C:\Program Files\Unisys\ABSuite8.0\bin64\X86\:

- mcutil.dll
- mcletsj.dll
- mbcconv.dll
- eudcserv.dll

Windows Compatibility

The AB Suite 8.0 software is qualified for Windows Server 2019 Datacenter Edition and Windows 10 Professional, Enterprise (x64)

The AB Suite 8.0 software is qualified for the following database on Windows Server 2019 Datacenter and Windows 10 Professional, Enterprise (x64)

- SQL Server 2019 Enterprise Edition

The AB Suite 8.0 software is also supported on the following databases on different Windows operating systems

For AB Suite Developer

- SQL Server 2019 Express, Developer, Standard are supported on:
 - Windows Server 2019 Standard, Datacenter (LTSC) v1809
 - Windows 10 Professional, Enterprise (x64) May 2020 Update

Note:

- *AB Suite is qualified using the latest security patches and updates that are available at the time of qualification. It is recommended to use the most recent security patches and updates from Microsoft.*
- *AB Suite 8.0 currently supports 64-bit Windows 10, Windows Server 2016 (LTSC versions), and Windows Server 2019 (LTSC versions) only. It does not support 32-bit Windows. Windows Server Semi-Annual Channel versions, such as version 1709, 1803, and 1809 are not currently supported.*
- *AB Suite 8.0 currently supports SQL Server 2019 only. Please contact AB Suite Support if you require support for an older level of SQL Server.*
- *Microsoft OLE DB Driver 18 for SQL Server is required for AB Suite 8.0 Administration Tool, as previous OLEDB drivers do not support TLS 1.2. Please download 64-bit drivers and install them from. TLS 1.2 or later is required, earlier TLS and SSL levels are not supported.*

For AB Suite Runtime

- SQL Server 2019 Enterprise Edition is qualified on:
 - Windows Server 2019 Datacenter Edition (LTSC)
 - Windows Server 2022 Datacenter Edition (LTSC)
- SQL Server 2019 Enterprise Edition is supported on:
 - Windows Server 2019 Standard
 - Windows Server 2019 Standard Datacenter Edition v1809 (LTSC)

Installation Problem Reporting

Because Agile Business Suite relies on the underlying operating system and network software, details of the environment are vital to the resolution of problems. When reporting problems, ensure the following information is supplied:

- The operating system and version number used on the workstations, for example, Windows Server 2019 Datacenter Edition (LTSC) installed.
- All networking software and versions, the network server software and level, and the workstation client software and version.
- Error and log files.

Prerequisites for Installing in VDI Environment

In Windows Server 2019 Datacenter Virtual Desktop Infrastructure (VDI) that does not have internet connectivity, you might encounter installation issues while installing AB Suite Developer, Client Tools Component enabler, Runtime, Presentation Client, and Business Integrator. The installation issues might be related to the missing certificates, which need to be imported into the VDI environment. You must export the following certificates from a machine that has internet connectivity and then import them into a machine where AB Suite is installed in a VDI environment without internet connectivity:

- VeriSign Class 3 Public Primary Certification Authority - G5
- GlobalSign Root CA

Note: You can also use the *signtool* utility against the AB Suite installed CAB files to verify the missing files.

Installing Agile Business Suite in a Distributed Runtime Configuration

Agile Business Suite can be installed on a network as a distributed system, with a Runtime Server, a Database Server and one to many Developer workstations. Developer can also be installed on the Runtime Server or the Database Server as required.

To install Agile Business Suite in a distributed runtime configuration, refer to the following sections:

- [Configuring Users and Network Communications](#)
- [Installing Visual Studio](#)
- [Installing Agile Business Suite Runtime](#)
- [Installing Agile Business Suite DB Migrate Utilities](#)
- [Installing Agile Business Suite Developer](#)
- [Installing SQL Server 2019](#)

When you run the executable file, it reads the configuration file specified in the Target box to set up the connection parameters required to connect to the runtime system.

Once the distributed system is installed, to deploy an application to a distributed configuration:

1. Create, import, or open a model in Agile Business Suite Developer.
2. Configure the Business Segment to be deployed for remote deployment.
3. In the Installation section of the Segment's deployment properties, set the deployment host to the remote host.
4. Configure the Business Segment to use the remote Database Server registration.

In the Persistence section of the Segment's deployment properties, set the Database Server Registration to the mapping created on the remote runtime server.

Configuring Users and Network Communications

Before installing Agile Business Suite and supporting software, you need to create user accounts and configure them in the active directory of the domain controller, by performing the following

1. In the user properties for your domain Application Administrative User, on the Delegation tab, select **Trust this user for delegation to any service (Kerberos only)** option (this option might differ depending on your operating system).

Note: In Windows Server 2010 and later version domains, to provide delegation privileges to the Application Administrator User account and mark it as "Account trusted for delegation", you should assign Service Principal Name (SPN) to the Application Administrator User account in the active directory.


For example, to assign an SPN name 'https/AppAdminUser' to AppAdminUser account, run the following setspn command on domain controller:

```
setspn -a https/AppAdminUser AppAdminUser
```

where, the first parameter, https/AppAdminuser, is an SPN name and the second parameter, AppAdminUser, is an account name.

You can also prefix a domain name with the account name, for example,

```
setspn -a https/AppAdminUser MyDomain\AppAdminUser
```



2. If you are using Web Services, install IIS on the Runtime Server.

Agile Business Suite 8.0 supports Web services on the Windows runtime in an IIS 10.0 environment.

The IIS 10.0 Web Server is available on the following platform:

- Windows Server 2019

Note that the IIS 6 Management Compatibility component needs to be installed for Web Services to work on IIS 10.0. The IIS 6 Management Component includes:

- IIS Metabase and IIS 6 configuration compatibility
3. If you are using MSMQ protocol adapters, install Message Queueing on the Runtime Server.
 4. On the Database Server, you need to enable the Application user to remotely launch and activate COM+ applications.
 5. Add the Application Administrative User to the Administrators group on the Runtime and Developer Servers. Refer to [Preparing for Installation of Agile Business Suite](#) for more information.
 6. Configure the local security policy for the Application User and the Application Administrative User as described in [Preparing for Installation of Agile Business Suite](#)
 7. Add the Application User and Application Administrative User to the Distributed COM Users local group and the Network Access local group on the Runtime and Developer Servers.
 8. Enable Distributed COM on the Application Server and the Development Server by performing the following:
 - a. Point to the bottom-left corner of the screen to enable the Start icon, right-click **Start**, and then click **Run**.
 - b. Type dcomcnfg in the Run dialog box and then press **Enter**.
The Component Services window appears.
 - c. In the left pane, expand **Component Services** and then expand **Computers**.
 - d. Right-click **My Computer** and select **Properties** from the context menu.
The **My Computer Properties** dialog box appears
 - e. On the **Default Properties** tab, select **Enable Distributed COM on this computer**.
 - f. Click **OK**.

Installing Visual Studio

Install Visual Studio 2019 or higher on each developer machine. Windows Server 2019 also installs the matching .NET Framework version 4.8.

Note: You must use the recent security patches and updates from Microsoft.

Installing Agile Business Suite Runtime

Install the full Agile Business Suite Runtime on the Runtime Server with the following custom options:

- Runtime
- AdminTool

Installing Agile Business Suite DB Migrate Utilities

The installation of AB Suite DB Migrate Utilities allows AB Suite DB Migrate Utilities for SQL Server 2019 to be installed on a standalone SQL Server Database Server. This installation allows DB migrate utilities to import runtime data from EAE. Install Agile Business Suite DB Migrate Utilities component on the Database Server with the following custom options:

- AdminTool
- DB Migrate Utilities

You can view these options when you install Runtime on your workstation.

Installing Agile Business Suite Developer

Install Agile Business Suite Developer on each Developer workstation.

Installing SQL Server 2019

Install SQL Server 2019 Enterprise Edition on the Database Server and any Developer workstation. Ensure that the following components are also installed.

For database migration install:

- Integration Services
- Analysis Services
- Database Engine Services

For the enterprise management tools install:

- Management Tools (SQL Server Management Studio is installed separately)

Installation of SQL Server 2019 does not add the BUILTIN\Administrators group as a sysadmin by default. This affects the creation of runtime databases via the Runtime Administration Tool.

You can perform either one of the following to overcome this situation:

- Specify the BUILTIN\Administrators group in the Database Engine Configuration dialog box during the installation of the SQL Server 2019.
- Add the Application Administrative User account as sysadmin in SQL Server 2019. You need to do this for every Instance of SQL Server 2019.

Distributing Configuration Files

You can connect the Direct Connect client applications, such as Winforms and Client Framework to the AB Suite runtime system running on a different machine in the same domain.

To connect the Direct Connect client applications to the AB Suite system running on a remote machine, perform the following:

1. Share the folder where you have stored the configuration file on the network.
2. Modify the following tags in the configuration file:
 - `<RuntimeServer>` – Set this tag to the machine name where the runtime system is deployed. This can also be the IP address of the server.

For example, `<RuntimeServer>ustr-erl2-9999</RuntimeServer>`

- `<DownloadServerUrl>` – Set this tag to the location where the DLLs that implement the client forms are located.

For example,

If you want to connect the Winforms to the AB Suite runtime system on a different machine, you must modify the `<DownloadServerUrl>` tag in the Winform config file (for example, `Ispec.xml`) as follows:

```
<DownloadServerUrl>\<IP Address of Remote Runtime
System>\<SharedFolderName>\<configuration name>\<segment
name>\Interfaces\Winforms\ Core\Bin </DownloadServerUrl>
```

If you want to connect the WPF Client to the AB Suite Client Framework runtime system on a different machine, you must modify the `<DownloadServerUrl>` tag in the WPF Client config file (for example,

`<TechnologyFolderName>_Config.rtxml`) as follows:

```
<DownloadServerUrl>\<IP Address of Remote Runtime System>\<Visual
Studio Projects Folder>\<Solution name>\Access Layer API Deploy</
DownloadServerUrl>
```

Notes:

- A default Winform config file, `Ispec.xml`, is generated when you build the AB Suite application in the following location:

```
<package installation directory>\<configuration name>\<segment
name>\Core\Bin\Ispec.xml
```
- A default WPF Client configuration file, `<TechnologyFolderName>_Config.rtxml`, is generated when you build the AB Suite Client Framework application in the following location:

*<Visual Studio Projects Folder>\<solution name>\Access Layer API
Deploy\<TechnologyFolderName>_Config.rtxml*

You can copy the configuration files to a different location on the system and customize it as per your requirement.

3. Ensure that the standalone Client Framework or Winform Client is installed on the client machine.
4. Create a shortcut of the executable file on the desktop of the client machine.

Note: When a 32-bit standalone Client Framework or Winform Client is installed, the executable file is located in the following path:

C:\Program Files (x86)\Unisys\AB Suite 8.0\Bin

When a 64-bit standalone Client Framework or Winform Client is installed, the executable file is located in the following path:

C:\Program Files\Unisys\AB Suite 8.0\Bin

5. Right-click the shortcut, and select **Properties**.

The **Properties** dialog box appears.

6. In the **Target** box, enter the IP address of the client machine and the location of the configuration file.

For example, <IP Address of Client Machine>\

C:\Users\appadminuser\Documents\Visual Studio 2019\Projects\<app name>\Access Layer API Deploy\WPF_Config.rtxml

7. Click **OK**.

When you run the executable file, it reads the configuration file specified in the Target box to set up the connection parameters required to connect to the runtime system.

Configuring for Distributed Deployment

To finalize the configuration for distributed deployment, perform the following:

1. On the Runtime Server, create a remote database server registration that points to the default instance of SQL Server on the Database Server machine.
2. Once you have created a database server registration, you can add new runtime databases or attach pre-existing databases. The Admin Tool detects any existing AB Suite databases, including the databases in the earlier releases and automatically re-attaches the databases to be used with AB Suite 8.0.

Section 3

Developer Installation

This section describes how to install Agile Business Suite Developer.

Required Software Configuration

The system software configuration required to support Agile Business Suite Development client workstations are detailed in the following table.


Required Software	Comments
- Windows Server 2019 Datacenter v1809 (LTSC) - Windows 10 Professional, Enterprise (x64) - Windows Server 2016 (LTSC versions)	AB Suite 8.0 currently supports 64-bit Windows 10, Windows Server 2016 (LTSC versions), and Windows Server 2019 (LTSC versions) only. It does not support 32-bit Windows. Windows Server Semi-Annual Channel versions, such as version 1709, 1803, and 1809 are not currently supported. Agile Business Suite 8.0 Developer runs in a 64-bit WOW64 environment.
- Visual Studio 2019 and - Azure DevOps Services	On 64-bit operating systems, Visual Studio 2017/2019 runs in WOW64 environment. Visual Studio Community Edition, Express Edition, and Test Professional Editions are not supported. Notes: - Visual Studio 2019 version can change frequently. Refer to the AB Suite 8.0 Software Qualification and Support Matrix for the updated Visual Studio 2019 version details. - When you install Visual Studio 2019, you have to select the required workloads and components necessary to support the installation of AB Suite 8.0. See Installation of Visual Studio 2019 for information on the components that you have to select when you install Visual Studio 2019. - AB Suite 8.0 is qualified with Visual Studio 2019 and Azure DevOps Services, and supports Azure DevOps Server 2020.

Developer Installation


Required Software	Comments
One of the following: - SQL Server 2019 Enterprise Edition - SQL Server 2019 Express, Developer, Standard	The installation proceeds successfully if SQL Server is not installed. However, before you start using Developer, you must either install a database server or have access to another machine with a database server installed. Notes: - SQL Server 2017/2012 Native Client is required for Developer installation that do not already have SQL Server installed locally. - AB Suite 8.0 currently supports SQL Server 2019. Please contact AB Suite Support if you require support for an older level of SQL Server. - If you are using SQL database, ensure that it is configured as described in SQL Server Configuration. - SQL Server 2019 need not be installed on a Developer workstation when the Model database is on another machine. However, it is required only when you need a local Model database. If the model database is on another machine, then SQL Server Native Client is a requirement for the Developer workstation.
Microsoft SQL Server Management Studio	No comments for this requirement.
Microsoft Visual C++ Redistributable for Visual Studio 2019 latest update	No comments for this requirement.
Microsoft OLE DB Driver for SQL Server	This is a mandatory software. Note: Microsoft OLE DB Driver for SQL Server need not be installed for MCP Runtime applications that use HDBA with Debugger sessions, because MCP Debugger sessions using HDBA uses Unisys OLE DB driver.
Microsoft SQL Server 2017/2012 Native Client	This is a mandatory pre-requisite for AB Suite Developer installations that do not already have SQL Server installed.
.NET Framework 4.8	.NET Framework 4.8 is required. Note: .NET 4.8 is supported and required on Windows Server 2019.
Java Software Development Kit v1.6 or later	This is used for generating Java based applications. Notes: Java Software Development Kit v1.8 is supported. This excludes custom generators.

Required Software	Comments
Enterprise Output Manager 13.0 (64-bit)	This is an optional supported application. Note: On 64-bit operating systems, EOM runs in WOW64 environment as it is a 32-bit application.

You can also run the AB Ready tool to check the status of the prerequisite software for Developer installation.



104068



Required Agile Business Suite Software

Due to the inter-relationships between the components of the Agile Business Suite software, the Agile Business Suite Runtime for Windows Release 8.0 software for the target host platform is required, if you wish to generate and deploy an Agile Business Suite system.

Installation of Visual Studio 2019

When you install Visual Studio 2019, you have to customize the installation by selecting the required features to support the installation of AB Suite 8.0.

To select the required features, perform the following:

1. Select the **Workloads** option.
 - a. Under **Desktop & Mobile**, select the following:
 - .NET desktop development
 - Desktop development with C++
 - b. Under **Web & Cloud**, select the following:
 - ASP.NET and web development
 - c. Under **Other Toolsets**, clear the **Visual Studio extension development** check box.

Note: If this option is selected, an error message appears when you install Developer and therefore you will not be able to proceed with the installation.

2. Select the **Individual Components** option.

The required components to support the installation of AB Suite 8.0 are selected automatically based on the features you select in the Workloads option. However, you have to select the following components manually:

- a. Under **.NET**, select the following components:
 - .NET Framework 4.7.2 SDK
 - .NET Framework 4.7.2 targeting pack
 - .NET Framework 4.8 SDK
 - .NET Framework 4.8 targeting pack
- b. Under **Code tools**, select the following components:
 - Help Viewer

Note: If you do not select Help Viewer, you cannot view the Developer online help in Help Viewer.

Minimum Hardware Requirements

Developer is installed on stand-alone workstations. Minimum requirements for this configuration are described below.

Workstations

Developer is an I/O intensive application because all objects are stored in the model and updated constantly as each object changes.

Windows is also I/O intensive when all applications cannot reside in memory. This means that disk transfer rates are a critical factor in workstation performance. Faster disk drives and increased RAM provides performance benefits.

The following table shows the minimum recommended hardware requirements for a workstation when Developer is installed, either on its own, or together with Builder or Version Control.

Hardware	Developer Workstation	Build Server	Runtime Server	Model Server
Processor	2 core, 2 GHz (x86)	2 core, 2 GHz (x86)	4 core, 2 GHz	2 core, 2 GHz (x86)
RAM	4 GB	4 GB	8 GB	4 GB
Disk space*	200 GB	200 GB	200 GB	200 GB

Developer Installation

Hardware	Developer Workstation	Build Server	Runtime Server	Model Server
Operating System	64-bit Client Operating System	64-bit Client Operating System	64-bit Server Operating System	64-bit Client Operating System
Other	SVGA or LCD monitor			

The following table shows the recommended hardware for a workstation:

Hardware	Developer Workstation	Build Server	Runtime Server	Model Server
Processor	Quad Core Intel Core i7 (equivalent or better)	Dual Core Intel Core i7 (equivalent or better)	Quad core configuration Intel i7/ Xeon (3 GHz) (equivalent or better)	Dual Core Intel Core i7 (equivalent or better)
RAM	16 GB or higher	16 GB or higher	16 GB or higher	16 GB or higher
Disk space*	500 GB	500 GB	400 GB Operating System Drive	500 GB
Operating System	64-bit Operating system	64-bit Server Operating System	64-bit Server Operating System	64-bit Server Operating System
Other	Large, wide-screen LCD monitor	LCD	Active Directory domain membership	

* Additional disk space is required if the Microsoft SQL Server database is stored on this machine. The required space varies depending on the size and complexity of the system.

For the Model Database

The disk space required for the model database depends on the size of the Specification being developed. This includes the number of <<Ispec>> classes, Reports, lines of logic, and Global Logics.

Due to the extensive re-engineering that has been carried out in this version of Developer, and the efficiency of the Microsoft SQL Server database, the disk space required for a Model database is significantly less than was required for previous releases of Enterprise Application Developer.

Preparing Your Network for Developer

Network traffic can be a significant factor in the overall performance of Developer with a multiuser SQL database.

Before installing Developer, you should tune your network to minimize traffic congestion. This ensures that your network handles the interaction between Developer and the database to provide optimum performance.

Access Rights to Drives, Directories, and Files

You must give the Application User and the Application Administrative User full read and write access rights to the drive and directory in which the Microsoft SQL Server database of a user is located.

The Application User and the Application Administrative User must have read and write access rights to their nominated working directories.

Access to Font Files

The Application User and the Application Administrative User must have read and execute access to the fonts that Developer uses. This is necessary in order to correctly display the fonts used in the Painter and the Logic Editor, and for creating Help screens. Developer uses these fonts: LINCDEFAULTNEW, and LINCDEFAULTNEWBOLD. These fonts are stored in the directory **C:\Windows\Fonts**.

Installing Developer on a Workstation

Developer can be installed on any workstation from the Unisys Installation Interface. It can also be installed to operate remotely by using the Microsoft Remote Desktop Services.

Prerequisites

Setting Access Rights

If the Developer installation process attempts to overwrite a system file and detects that you do not have Administrator access rights, an error message appears and the installation process exits.

Windows operating system access rights are set by the Computer Management program. This can be accessed by clicking the Administrative Tools (Common). If you are unable to set Windows operating system access rights, contact the System Administrator for your site. Note that if Active Directory is in use, you might need to set these permissions through a group policy.

Note: If the Developer installation process finds system files that requires to be updated, you are prompted to reboot your machine before running Developer.

On Windows 10 and later operating systems, you do not need to run Developer as an Administrator while using setup.exe for installation.

Refer to [Preparing for Installation of Agile Business Suite](#) for more information on how these user accounts can be created manually.

Disable Spyware Applications

If you are using any spyware application, such as Spy Sweeper or Ad-Aware, you have to disable it before executing the installation or uninstallation process.

Failure to do so might result in the following error:

1935 – An error occurred during the installation of assembly.

Performing the Developer Installation

After an administrator has created the required users and configured them correctly, you can begin the installation of Developer.

You can also create the required users when you are installing developer.

To install Developer, perform the following:

1. Double-click CDBrowser.exe.

The Unisys Installation Interface appears. This interface controls the installation process.

2. Click **Development Environment**.

The InstallShield Wizard appears.

Note: When this wizard appears, the installation program performs the prerequisite checks. If any of the prerequisite checks fail, then a message appears and the installation is terminated. If the checks are successful, you can continue with the installation.

3. On the InstallShield Wizard, click **Next**.
4. Select **I accept the terms in the license agreement** option, after you read and accept the terms in the license agreement, and then click **Next**.
5. Select the target drive and directory for the installation, if you do not want to accept the default installation location, and then click **Next**.

Note: You cannot install different versions of AB Suite Developer, such as 5.0, 6.1, 7.0, or 8.0 on the same machine.

6. Select either of the following setup type:

- **Complete**

Select this option to install the essential components of Developer and Target Builders. The Developer components consist of System Modeler, Debugger, Version Control Tools, Documentation, Builder, Automated Test Tool, Client Framework components, and Target Builders for Windows and MCP.

Notes:

- *Documentation*

If Microsoft Help Viewer is installed, Documentation feature is installed when System Modeler is installed on a workstation. When documentation is installed on your workstation you can view the AB Suite online help in help viewer.

- *Automated Test Tool*

The ATT package is installed when System Modeler is installed on a workstation. ATT supports recording of test cases for AB Suite applications and AB Suite Client Framework applications. If you want to record test cases with Component Enabler Client you need to install Component Enabler.

- *Client Framework*

Although all Client Framework components are installed when System Modeler is installed on a workstation, you might need to install additional development tools, such as Microsoft Blend, in your environment depending on the technologies you choose for developing your client applications.

- **Custom**

Select this option to customize the components that you want to install and click **Next**.

The following options appear:

- System Modeler
- Builders
- Documentation

System Modeler

This is a mandatory feature. It installs the Developer software, which includes all the functionally required in Developer.

Builders

Select this option to install the Builder software, which allows you to build and deploy an application in both Windows and MCP runtime environment.

The Builder software should be installed if you want to run the Debugger.

Documentation

Select the Documentation feature to install the AB Suite Documentation. When you install Documentation you can view the AB Suite Developer online help through the help viewer. However, Microsoft Help Viewer must be installed.

Note: You can also view the AB Suite online help through the browser even if you do not install the Documentation feature.

7. Click **Next** and select any of the following options to create a new Application User or to select an existing Application User:
 - Select an Application User from existing user accounts
 - Create a new Application User account.
 - Allow Installation to automatically create the Application User.

Select an Application User from existing user accounts

You can select this option when you have an Application User created prior to the installation.

To select an Application User from existing user account, perform the following:

- a. After you select, **Select an Application User from existing user accounts** option, click **Next**.
- b. Enter the following credentials for the Application User:
 - Domain Name — Enter the Domain name of which this user is a member. If the Application User is a local user, you can simply accept the period character for the domain name or enter the name of the local machine. However, if the user has been created as a member of a network domain, the name of that domain should be entered here. This could occur if the database that Developer connects to is on a machine other than the local machine.
 - User Name — You can either type the Application User Name or click Browse and select the Application User name from the Select a User Name dialog box.
 - Password — Enter the password for the user name on the chosen domain.

Create a New Application User Account

You can choose this option to create a new Application User.

To create an Application User, perform the following:

- a. After you select, **Create a New Application User Account** option, click **Next**.
- b. Enter the following credentials for the new Application User:
 - Domain — Displays the domain name of the computer. You can either retain the domain name or type ".".
 - User Name — Enter the new Application User name.
 - Password — Enter a password for the new Application User.
 - Confirm Password — Re-enter the password.
- c. Click **Create**.

A message box appears confirming the creation of the application user.
- d. Click **OK** on the message box.

Note: The local security policy user is automatically set by the installation. Refer to *Configuring the User Accounts* for more information.

Allow Installation to Automatically Create the Application User

You can choose this option to allow the installation to create a default Application User.

To automatically create an Application User, perform the following:

- a. After you select, **Allow Installation to Automatically Create the Application User** option, click **Next**.
- b. Enter the following credentials for the new Application User:
 - Display Name — Displays the domain name of your system.
 - User Name — Displays ABSuite80AppUser, which is the default user name created for AB Suite application user.

Note: You cannot edit the domain name and user name.

- Password — Enter a password for the new Application User.
 - Confirm Password — Re-enter the password.
- c. Click **Create**.

A message box appears confirming the creation of the application user.

Note: The new Application User is created by using this option only when it is used for the first time. If the user already exists in the system and you use this option, you will be prompted with a message – “The default user already exists. Please enter the password.”

- d. Click **OK** on the message box.

Note: The local security policy for the user is automatically set by the installation. Refer to *Configuring the User Accounts* for more information.

8. Click **Next** and select any of the following options to create a new Application Administrative User or to select an existing Application Administrative User:
 - Select an Application Administrative User from existing user accounts
 - Create a new Application Administrative User account.
 - Allow Installation to automatically create the Application Administrative User.

Select an Application Administrative User from Existing User Accounts

You can select this option when you have an Application Administrative User created prior to the installation.

To select an Application Administrative User from existing user account, perform the following:

- a. After you select, **Select an Application Administrative User from existing user accounts** option, click **Next**.
- b. Enter the following credentials for the Application Administrative User:

- **Domain Name** — Enter the Domain name of which this user is a member. If the Application Administrative User is a local user, you can simply accept the period character for the domain name or enter the name of the local machine. However, if the user has been created as a member of a network domain, the name of that domain should be entered here. This could occur if the database that Developer connects to is on a machine other than the local machine.
- **User Name** — You can either type the Application Administrative User Name or click **Browse** and select the Application Administrative User name from the Select a User Name dialog box.
- **Password** — Enter the password for the user name on the chosen domain.

Create a New Application Administrative User Account

You can select this option to create a new Application Administrative User.

To create an Application Administrative User, perform the following:

- a. After you select, **Create a New Application Administrative User Account** option, click **Next**.
- b. Enter the following credentials for the new Application Administrative User:
 - **Domain** — Displays the domain name of your system. You can either retain the domain name or type ".".
 - **User Name** — Enter the new Application Administrative User name.
 - **Password** — Enter a password for the new Application Administrative User.
 - **Confirm Password** — Re-enter the password.
- c. Click **Create**.

A message box appears confirming the creation of the application administrative user.

- d. Click **OK** on the message box.

Note: The local security policy user is automatically set by the installation. Refer to *Configuring the User Accounts* for more information.

Allow Installation to Automatically Create the Application Administrative User

You can choose this option to allow the installation to create a default Application Administrative User.

To automatically create an Application Administrative User, perform the following:

- a. After you select, **Allow Installation to Automatically Create the Application Administrative User** option, click **Next**.
- b. Enter the following credentials for the new Application Administrative User:
 - **Display Name** — Displays the domain name of your system.
 - **User Name** — Displays ABSuite80AppAdmin, which is the default user name created for AB Suite application user.

Note: You cannot edit the domain name and user name.

- Password — Enter a password for the new Application Administrative User.
- Confirm Password — Re-enter the password.

c. Click **Create**.

A message box appears confirming the creation of the application administrative user.

d. Click **OK** on the message box.

Note: The new Application Administrative User is created by using this option only when it is used for the first time. If the user already exists in the system and you use this option, you will be prompted with a message – “The default user already exists. Please enter the password.”

9. Click **Next**.

10. In the Data folder screen that appears, you can either install the data files to the default location, C:\AB Suite 8.0\Data\, or click **Change** to install the data files to a different location.

This is the location of the Runtime Data directory that stores various data files, such as log files and configuration files.

11. Click **Next**.

12. In the Builder Cache Folder that appears, select the path for the Builder Cache.

The compressed copies of files generated by Builder are stored in this location. This location can be changed after the installation is complete from the Tools, Options dialog box.

When systems are generated to any target platform and multiple workstations are used for this purpose, all workstations must use a shared directory. This ensures that all the shared workstations create, modify, and read the same files in the BuilderCache directory.

To do this, perform the following:

- a. Browse to the location of the BuilderCache directory.
- b. Right-click the BuilderCache directory, and select **Properties**. The **BuilderCache Properties** dialog box appears.
- c. Select the **Sharing** tab and choose **Share this folder** option.
- d. Click **Permissions** and add the remote user.
- e. In the Permissions for the BuilderCache, select the **FullControl** check box for the remote user.
- f. On the remote machine, add the shared BuilderCache directory as a mapped network drive.
- g. Set the network drive as the path for the BuilderCache directory during the Agile Business Suite installation on the remote machine.

In a multi user environment, it is recommended that all users select a shared location for the Builder Cache. This prevents unnecessary re-generates of already generated and unchanged files.

Setting the Builder Cache and Builder Output Path

You can set the builder cache path and the builder output path as follows:

Builder Cache Path

When you install AB Suite Developer, you can either set the builder cache path for All Users or for Current User only.

If you want to set the builder cache path for all users, clear the **Set the Builder Cache Path for this user** only check box. This check box is not selected by default.

If you want to set the builder cache path for the current user, select the **Set the Builder Cache Path for this user** only check box.

If there are any installation restrictions on using the C drive, you can change the builder cache path at this stage, during the installation, by clicking the **Change** button in the InstallShield Wizard.

Builder Output Path

The builder output path, however, can be changed from Visual Studio only. This change affects the Current User and not All Users.

To change the builder output path, perform the following steps:

- a. Start Visual Studio after the installation of AB Suite is complete.
- b. From the **Tools** menu, select **Options**.
The **Options** dialog box appears.
- c. In the left pane, expand **System Modeler**, expand **Builder**, and then select **General**.
- d. In the right pane, enter or browse to the location of your choice in the **Location of Build Output** box.

Note: You can also enter or browse to a location of your choice in the **Location of Cache for generated files** box.

If there are any restrictions on using the C drive, you can change the builder output path to an alternative drive of your choice.

13. Click **Next**.

14. In the Ready to Install the Program screen, click **Install** to begin the Installation.

If you want to change any of the installation settings you can click **Back** and change the settings. The Installing Agile Business Suite 8.0 Developer screen displays the progress bar.

At the completion of the installation, the Installation Complete Screen appears.

This screen displays the following options:

- **Show the readme file** — displays the readme file when you select the check box and click Finish. You can clear the check box if you do not want to view the readme file. This check box is not selected by default.
- **Show the Windows Installer log** — display the AB Suite <version>

Runtime.log file when you select the check box and click Finish. You can clear the check box if you do not want to view the log file. This check box is not selected by default.

15. Click **Finish** to complete the installation.

Silent Installation

The Developer Installation Package is in the .msi format and supports Silent Installation through the use of the msixec.exe utility. When the command line argument "/qn" is passed to the utility, the installation of the Developer Installation Package proceeds without Graphical User Interface (GUI) that is, there are no dialog boxes or user prompts requesting for information, such as the installation directory. The progress of the installation, indicating success or failure, is written to a log file. The log file includes the status, warnings, and error messages.

Performing Silent Installation of Developer

To install the Developer Installation Package in silent mode, execute the following command from the command prompt:

```
"> msixec.exe /i "<path of the AB Suite 8.0 Developer.msi>\AB Suite8.0 Developer.msi" /
qn <parameters>"
```

The commands or parameters to execute the AB Suite package are as follows:

Commands or Parameters	Values
msixec /i	Example: <default>\AB Suite 8.0 Developer\Product Configuration 1\Release 1\DiskImages\Disk1\AB Suite 8.0 Developer.msi
/qn INSTALLDIR =	Example: C:\Program Files\Unisys\AB Suite 8.0\
AgreeToLicense	Yes
ADDLOCAL	ALL
PASSAPPUSERDOMAIN=	.
PASSAPPUSER=	Example: AppUser
PASSAPPPASSWORD=	Example: App1User
PASSAPPADMINDOMAIN=	.
PASSAPPADMIN=	Example: AppAdminUser
PASSADMINPASSWORD=	Example: App1AdminUser
PASSDATA=	Example: C:\AB Suite 8.0\Data\
/l*v	Example: C:\Temp\AB Suite 8.0.Log

Where,

msiexec is the executable program of the Windows Installer to interpret installation package and install products on the target location.

/i switch is used to install the package from the command line.

/qn switch is used to suppress the dialog boxes displayed for input and output to the user.

INSTALLDIR is a property for specifying the location where the Windows Installation Package is installed.

/l*v switch is used to create a log file.

Following is an example to install Developer through Silent Installation from the command prompt:

```
msiexec.exe/i
/qn/ norestart INSTALLDIR="C:\Program Files\Unisys\AB Suite 8.0\" AgreeToLicense=Yes
ADDLOCAL=ALL PASSAPPUSERDOMAIN="." PASSAPPUSER="AppUser" PASSAPPPASSWORD="AppUser"
PASSAPPADMINDOMAIN="." PASSAPPADMIN="AppAdminUser" PASSADMINPASSWORD="AppAdminUser"
PASSDATA="C:\AB Suite 8.0\Data\" /l*v "C:\TEMP\AB Suite 8.0 Developer.log"
```

Installing Developer with Windows Remote Desktop Services

It contains instructions on how to install and configure Developer with Microsoft Windows Server 2019 and above Remote Desktop Services.

Note: *Remote Desktop Services installation is recommended when you want to use a shared model database and have all the development environments on the same physical machine.*

What are Remote Desktop Services?

Remote Desktop Services allows a single server to be used for multiple users, with each user having a separate virtual environment on the Remote Desktop Services server. All processing is performed by the Remote Desktop Services server.

Users access the server using a client containing only the minimum software necessary to boot the device, establish a connection to the server, and present the user interface. This type of client is sometimes called a Thin Client.

Windows Server 2019 provide integrated support for a Thin Client environment in the form of Windows Server 2019 Remote Desktop Services.

Recommended Configuration

Configure a Remote Desktop Services server installation on a Windows network so that all users who log in to the network and use a Remote Desktop Services client session are able to use required Developer components.

In this recommended configuration:

- Users log in to the Local Area Network (LAN) using a Windows Remote Desktop Services client session and start Developer. Dial-in connections, as well as direct connections, might be used.
- Developer clients connect to the Developer application on the network.

Requirements for a Remote Desktop Services Installation

Before installing and configuring Remote Desktop Services, ensure you have the following:

- A network directory (usually a location on the file server), from which a Developer client installation can be performed.
- A machine with Microsoft Windows Server, connected to the network, on which the Version Control Server (if required) and Model database are to be installed. This is referred to as the Server machine.
- A machine with Microsoft Windows Remote Desktop Services installed and connected to the network. This is referred to as the Remote Desktop Services server.
- A *Root Drive* for each user on the network, which is mapped to the user's home directory on the network. For example, each user has drive letter H: as the root drive mapped to a directory on the Developer Server machine. It is represented by the %ROOTDRIVE% environment variable on the Remote Desktop Services server.

Installation Procedure

For the purposes of this example installation, it is assumed that:

- Each user's *Root Drive* (%ROOTDRIVE% variable) is mapped to drive letter H:.
- The %SYSTEMROOT% environment variable on the Remote Desktop Services server is set to C:\Wtsrv.
- Required user accounts have been created on the Remote Desktop Services server.

Setting Access Rights

In order to install Developer on a Windows Remote Desktop Services server, you need to have **Administrator** access rights to the Remote Desktop Services server. This is required because some Windows system files might be overwritten during installation, and only users with Administration access rights have permission to overwrite system files.

If the Developer installation process attempts to overwrite a system file and detects that you do not have Administrator access rights, an error message is displayed and the installation process exits.

Windows operating system access rights are set by Computer Management MMC snap-in. You can access this by pointing to and clicking the **Start** icon in the bottom-left corner of the screen, right-clicking a blank part of the **Start** screen, selecting **All apps**, and then clicking **Administration Tool** under **Agile Business Suite 8.0**. Alternatively, after clicking the **Start** icon, type **Administration Tool** on the desktop to locate and select the application from the **Start** screen. If you are unable to set Windows operating system access rights, see the System Administrator for your site.

Note: *If the Developer installation process finds system files that need updating, you will be prompted to reboot your machine before running Developer.*

Installing Remote Desktop Services

1. When installing Windows Server 2019 on your Remote Desktop Services server machine, you must install the following components:
 - **Remote Desktop Services**
 - **Remote Desktop Services Licensing**
2. After selecting these components, the Remote Desktop Services Setup screen displays a choice of Remote Desktop Services modes. Select **Application Server mode**. This mode is recommended for Developer, because it means that client machines can only install programs using the Remote Desktop Services server (using Add/Remove Programs in the Windows Control Panel).

Note: *To use Application Server mode, you must install a Remote Desktop Services licensing server in your domain within 90 days. Refer to Windows documentation for more information.*

3. Once the Remote Desktop Services mode has been selected, set the default permissions for application compatibility.

Options available in Windows Server 2019

- **Full Security**

This option uses the latest Windows Server 2019 security features and provides the most secure environment for your Remote Desktop Services. However, some applications that were designed to run on earlier platforms might not run properly. You can use the Remote Desktop Services Configuration tool to relax security at any time if this option proves to be too restrictive.

- **Relaxed Security**

This option lessens many of the security enhancements in Windows Server 2019. Under this configuration, users have access to critical registry and system file locations. This might be necessary in order to run some applications that were designed for earlier platforms.

The Developer installation is not affected by this option, so you should select an option based on the number of other legacy programs you are running, and the level of security required.

4. When you have selected your default permissions, continue with the standard Windows Server 2019 installation.

Creating Client Install Disks

Once Remote Desktop Services is installed on the server machine, create installation disks for the client machines.

To create the disks, perform the following:

1. Log in to the Remote Desktop Services server.
2. Select **Control Panel > Administrative Tools > Remote Desktop Services Client Creator**.
3. In the Create Installation Disk(s) dialog box, select Remote Desktop Services for 32-bit x86 windows. Click **OK** to finish creating the disks.

Use the created disks to install the Remote Desktop Services Client on your client machines.

Developer with Remote Desktop Services Installation and Configuration

To install Developer on the Remote Desktop Services server and to configure it for client use, perform the following:

1. Log in to the Remote Desktop Services server, then select **Programs and Features** from the Windows Control Panel.
 2. Locate and open the Developer installation program (CDBrowser.exe) and click **Install**.
- Note:** If User Account Control setting is set to Always Notify, run the program as administrator.
3. In the wizard dialog select the **All users begin with common application settings** option and click **Next** to start the Developer installation.
 4. Select the **Custom Installation Type** and click **Next**.
 5. In the Select Components dialog box, select only those components users need for a multiuser installation (for example, Developer). When complete, click **Next**.

If required, the Version Control and Builder can be installed later.

6. Enter the following data in the Installation Configuration dialog box:
 - In the Installation Directory field, enter the location on the Remote Desktop Services server where Developer is to be installed.
 - In the Working Directory field, enter the path to the user's Root Drive, for example, C:\Program Files (x86)\Unisys\AB Suite 8.0.
7. When the installation process is complete, click **OK**.
8. Return to the Programs and Features dialog box and choose **Next**, then **Finish**.
9. Restart the Remote Desktop Services server.

Note: *There should be separate copies of project and solution files for every user in the Remote Desktop Server and they should not be shared between the users.*

The Remote Desktop Services installation process is now complete.

Uninstalling Developer with Remote Desktop Services

To uninstall Developer, perform the following:

1. Select **Programs and Features** from the **Control Panel**.
2. Navigate to the Developer program folder, right-click and select **Uninstall**.
3. Click **Next** in the AB Suite Developer-InstallShield Wizard and select **Remove** and follow the Wizard.

Known Issues with Developer on Windows Remote Desktop Services

- Some issues might arise with auditing, changing management, and Version Control operations because on a Remote Desktop Services server installation, the machine name logged by Developer is the same for each user. To obtain usable audit information, it is recommended that Security is turned on so that both the user-id and machine name are logged.
- Each user can have multiple Remote Desktop Services server client sessions running, but should use a different username to log on to the Remote Desktop Services server to use Developer.
- The Remote Desktop Services server machine is generally not recommended for Primary or Backup Domain Controller.

Verifying Your Installation

To ensure your installation is correct, it is recommended that you create a new AB Suite project by using the sample AB Suite application or the sample AB Suite User Experience mode application from the templates provided in the New Project dialog box. You can then test the functionality with the sample model, create a build configuration, and then build and run the sample application.

Note: *The following verification steps are performed on the Windows platform.*

It is recommended to use the default Visual C# Development setting in Visual Studio for AB Suite Developer. This setting ensures that the entire shortcut keys work as expected in System Modeler. To set Visual C# Development Settings as a default setting in Visual Studio 2019, you must set or reset your profile.

Note: *A profile is a pre-defined settings collection you want to set the IDE to use.*

To set or reset your profile, perform the following:

1. On the **Tools** menu, select **Import and Export Settings**.
2. On Welcome to the Import and Export Settings Wizard page, click **Reset All Settings**, and then click **Next**.
3. On the Save Current Settings page, select **Yes, save my current settings**, and then click **Next**.
4. On the Choose a Default Collection of Settings page, select **Visual C# Development Settings** from the list, and then click **Finish**.

Creating an AB Suite Test Project

You can create an AB Suite test project by using the sample AB Suite application from the templates provided in the **Create a new project** dialog box for testing the functionality of the AB Suite Developer. You can then set the configuration properties, create a test database, build, and run the application.

To create an AB Suite project by using the sample AB Suite application, perform the following:

1. Open Visual Studio as an Administrator.
2. From the start window, select **Create a new project**.
If Visual Studio is already open, from the **File** menu, point to **New**, and then select **Project**. The **Create a new project** window appears.
3. Select **Sample Application** by performing one of the following options:
 - Filter AB Suite project templates from the available project templates by selecting **LDL+** from the **All languages** filter, select **MCP**, or **Windows** from the **All platforms** filter, or select **AB Suite** from **All project types** filter.
 - Use the **Search** box to filter the project templates. For example, type **Sample Application** in the search box to narrow down on the exact project template.
 - You can also use the **Recent project templates** available on the left if you have already opened the project. This is sorted based on most recently opened projects.
4. Click **Next**.
The **Configure your new project** window appears.
5. In the **Project name** box, enter the project name.
6. In the **Location** box, enter the path or browse to the location where you want to store the new project.
7. In the **Solution name** box, enter the solution name.
8. Click **Create**.
The **New Application Wizard** appears.
9. From the **Server Name** list, select the SQL server. By default, this list box displays the system name.

10. In the **Database Name** box, enter the model name. By default, this text box displays the solution name.
11. In the **Model Name** box, enter the model name. By default, this text box displays the solution name.
12. Click **Next**.

The project creation confirmation message appears in the wizard.
13. Click **Finish**.

The sample AB Suite application is restored.
14. Click **Close**.

The AB Suite project is created in the specified location and the sample AB Suite model node appears in the Class View window.

Creating a Deployment Folder

The SAMPLE.model file contains a deployment folder with pre-defined configuration properties. If you are using a model file without a deployment folder you must perform the following:

1. Right-click the model node in the Class View window, point to **Add**, and then select **Folder** from the context menu.

A folder with the default name "Folder1" is created under the model node. This folder can be used as a container for configuration properties.
2. Drag the segment into the deployment folder to apply these configuration properties to the segment.

A newly created deployment folder contains default settings. These settings must be modified to allow the sample application to be deployed successfully.
3. Rename the deployment folder from "Folder1" to an appropriate name. For example, "SampleDeploy".

Configuring the Deployment Folder

You must configure the deployment folder before you build the application.

To configure the deployment folder, perform the following:

1. Right-click the deployment folder and select **Properties** from the context menu.

The **<Deployment Folder Name> Property Pages** dialog box appears.
2. From the **Configuration** list, select **Release**.
3. From the **Platform** list, select **Windows**. By default, this property is set to **MCP**.
4. Under the **Build Target Filter** section, set the **Deployable** property to **True**.

This enables the other configuration properties.

5. Under Builder Target Filter section, set the **Deploy Application Components**, **Deploy Database**, **Deploy Reports**, and **Deploy Winform User Interface** properties to **True**.
6. Under Installation section, set the **Deployment Host** property to "localhost" for local deployment (where Runtime and System Modeler are installed on the same physical machine).
7. Browse to and select the **Package Installation Directory** where the deployable unit should be installed on the runtime server. For example, "C:\Program Files (x86)\Unisys\AB Suite 8.0\Sample". This is the location of all executable files for the deployed system.
8. Browse to and select the **Package Intermediate Directory** where you want to store the temporary installation files. For example, "C:\NGENSystems\Temp".
9. Click **OK**.

Configuring the Segment

To configure the segment, perform the following:

1. Right-click the segment and select **Properties** from the context menu.
The **<Segment Name> Property Pages** dialog box appears.
2. From the **Configuration** list, select **Release**.
3. From the **Platform** list, select **Windows**. By default, this property is set to **MCP**.
4. Set the **Database Name** to specify the runtime database name for the application. For example, "SAMPLEDB".
5. Set the **Database Server Registration** to specify the database server instance alias name defined in the Administration Tool. You can use a default instance named "default".

You must then create a runtime database (for example, "SAMPLEDB") by using the Runtime Administration Tool.

Creating a Runtime Test Database

To create a runtime test database, perform the following:

1. Point to and click the **Start** icon in the bottom-left corner of the screen.
2. Right-click a blank part of the **Start** screen and then select **All apps**. Select **Administration Tool** under **Agile Business Suite 8.0** or type **Administration Tool** on the desktop.
The AdminTool window appears.
3. Right-click **Favorites** and select **Add Server...**
The **Add Server to Favorites** dialog box appears.
4. Enter the local server name in the **Server name** box.
The server name appears under Favorites.

5. Expand the server you added and locate the “default” server registration node. If the “default” server registration node does not exist, perform the following:
 - a. Right-click the server node, point to **All Tasks**, and then select **Register Database Server**.
The **Register DB Server** dialog box appears.
 - b. In the **DBMS registration** alias name box, enter “default”.
 - c. In the **Server machine** box, enter the name of your local server.
 - d. In the **Instance name** box, enter the SQL named instance. If you are using a default instance.
 - e. Click **OK**.
6. Right-click the “default” server node, point to **New**, and then select **Database...**, to add a new SQL Server database. For example, enter “SAMPLEDB” as the database name.

Note: You must install SQL Server Management Studio (SSMS) and add the application administrative user to the MSSQL Server login as sysadmin before creating the runtime test database. If you do not perform this the authentication fails and you are prompted to add the application administrative user to the MSSQL Server login as sysadmin.

Building the Application

To build the application, perform the following:

1. Open the Class View window and select the top-level deployment folder.
2. Right-click the deployment folder, and select **Build**.

Note: You must install AB Suite Runtime before you try to build an application.

You must enter the Application User Name and password to build the application. Refer to Preparing for Installation of Agile Business Suite for more information on setting up an administrator account. If deploying locally, enter the Domain as “.”. The progress of the build operation appears in the Output window.

The build places all the deployed executable files in a series of sub-folders within the folder defined in the “Package Installation Directory” property. If this property is not defined, the executable files are stored in the default location, which is in a folder within the folder where the Agile Business Suite software is installed. For example, C:\Program Files (x86)\Unisys.

The contents of these folders are as follows:

- Database tables – The database tables are created within the SQL Server database.
- Winform dlls – The Winform dlls (one per ispec) can be located in
..\Sample\Interfaces\Winforms\Bin\<language number> within the folder structure.
- Application Component dll – The application component dll can be located in
..\Sample\Core\Bin.

The application is installed as a COM+ application.

Testing the Application

Refer to the *Agile Business Suite Developer User Guide* to run debugger and test that the application works correctly.

If you want to run the sample application by using the Winform client installed with AB Suite Developer, you must edit the ispec.xml file that is generated by the system. Refer to *Configuring Winform* for more information. The config.xml file is located at <Developer installation folder>\Unisys\AB Suite 8.0\Bin.

Creating an AB Suite Client Framework Test Project

You can create an AB Suite Client Framework test project by using the sample AB Suite User Experience mode application from the templates provided in the **Create a new project** window and test the functionality of the AB Suite Developer. You can then set the configuration properties, create a test database, build, and run the application

To create an AB Suite Client Framework test project by using the sample AB Suite User Experience mode application, perform the following

1. Open Visual Studio as an Administrator.
2. From the start window, select **Create a new project**.
If Visual Studio is already open, from the **File** menu, point to **New**, and then select **Project**.
The **Create a new project** window appears.
3. Select **Sample User Experience mode Application** by using one of the following options:
 - Filter the AB Suite project templates from the available project templates by selecting **LDL+** from the **All languages** filter, select **MCP**, or **Windows** from the **All platforms** filter, or select **AB Suite** from **All project types** filter.
 - Use the **Search** box to filter the project templates. For example, type **Sample User Experience mode Application** in the search box to narrow down on the exact project template.
 - You can also use the **Recent project templates** available on the left if you have already opened the project. This is sorted based on most recently opened projects.
4. Click **Next**.
The **Configure your new project** window appears.
5. In the **Project name** box, enter the project name.
6. In the **Location** box, enter the path or browse to the location where you want to store the new project.
7. In the **Solution name** box, enter the solution name.

8. Select **Place solution and project in the same directory** if you want to place both project and solution files in the same folder.

Note: If you enter a solution name that is different from the project name and then select the **Place solution and project in the same directory** check box, the solution name in the **Solution name** box will change to the project name specified in the **Project name** box. Furthermore, the solution name in the **Solution name** box appears dimmed.

9. Click **Create**.

The **New Application Wizard** appears.

10. From the **Server Name** list, select the SQL server. By default, this list box displays the system name.
11. In the **Database Name** box, enter the model name. By default, this text box displays the solution name.
12. In the **Model Name** box, enter the model name. By default, this text box displays the solution name.
13. Click **Next**.

The project creation confirmation message appears in the wizard.

14. Click **Finish**.

The sample AB Suite User Experience mode model is restored.

15. Click **Close**.

A Client Framework project is created in the specified location and the model node appears in the Class view window.

After creating the AB Suite Client Framework project by using the sample AB Suite User Experience mode application, you might have to configure a deployment folder. The NewSampleSys.model contains a deployment folder with pre-defined configuration properties. Refer to Creating a Deployment Folder for more information on creating a deployment folder, if you are using a model file without a deployment folder.

Configuring the Deployment Folder

You must configure the deployment folder before you build the application.

To configure the deployment folder, perform the following:

1. Right-click the deployment folder and select **Properties** from the context menu.
The **<Deployment Folder Name> Property Pages** dialog box appears.
2. From the **Configuration** list, select **Release**.
3. From the **Platform** list, select **Windows**. By default, this property is set to **MCP**.
4. Under the Build Target Filter section, set the **Deployable** property to **True**.

This enables the other configuration properties.

5. Under Builder Target Filter section, set the **Deploy Application Components**, **Deploy Database**, and **Deploy Reports** properties to **True**.
6. Under Installation section, set the **Deployment Host** property to "localhost" for local deployment (where Runtime and System Modeler are installed on the same physical machine).
7. Browse to and select the **Package Installation Directory** where the deployable unit should be installed on the runtime server. For example, "C:\Program Files (x86)\Unisys\AB Suite 8.0\Sample". This is the location of all executable files for the deployed system.
8. Browse to and select the **Package Intermediate Directory** where you want to store the temporary installation files. For example, "C:\NGENSystems\Temp".
9. Click **OK**.

You can now perform the following:

1. Configure the segment
2. Create a runtime test database
3. Build the application

Note: You must install AB Suite Runtime to build an application.

Refer to [Creating an AB Suite Test Project](#) for more information.

Testing the Client Framework Application

The sample Client Framework Model includes a set of designed XAML Views for the Sample system. You can use the supplied Views to test the deployed Client Framework application with the WPF Client.

To run the WPF Client against the AB Suite Client Framework application, you might have to edit the <Technology Folder Name>_Config.rtxml file. The configuration file is located at <System Modeler project folder>\Access Layer API Deploy. See [Installing Client Framework](#) for more information on the tags that you must edit in the <Technology Folder Name>_Config.rtxml file.

Verifying and Viewing Online Help

To verify if the AB Suite online help is installed and to view the help, perform the following:

1. Open Agile Business Suite 8.0 Development Environment.
2. If you have installed Help Viewer on your machine, perform the following:

On the **Help** menu, point to **Set Help Preference**, and then select either of the following:

- **Launch in Browser** – Select this option if you want to view help in information center.
- **Launch in Help Viewer** – Select this option if you want to view help in help viewer.

The AB Suite online help appears in the Information Center or in the Microsoft Help Viewer depending on the preference you select. You can press F1 on the keyboard to view context specific information.

Notes:

- *The Set Help Preference option is visible only if you install Help Viewer.*
- *Help Viewer is not installed by default when you install Visual Studio 2019. You must select this component when you install Visual Studio 2019 or install it later from the Visual Studio Installer. Refer to MSDN documentation for more information on installing Microsoft Help Viewer.*

If you have not installed Help Viewer on your machine, perform the following:

On the **Help** menu, click **View Help**.

The AB Suite online help appears in the Information Center or in the Microsoft Help Viewer depending on the preference you select. You can press **F1** on the keyboard to view context specific information.

Known Issues with Windows Server 2016

When Developer is installed on Windows Server 2016, help viewer displays HTML text as MIME Sniffing is disabled in the security settings of Internet Explorer, by default.

Workaround

To display Developer online help in the help viewer, perform the following after closing help viewer:

1. In Internet Explorer, click **Internet Options** on the **Tools** menu or select **Tools** button, and then select Internet options.
The **Internet Options** dialog box appears.
2. Select the **Security** tab and click **Custom level...**
3. In the **Security Settings - Internet Zone** dialog box, select **Enable** for **Enable MIME Sniffing** in **Miscellaneous** section.
4. Click **OK** to close Security Settings - Internet Zone dialog box.
5. Click **OK** to close Internet Options dialog box.

Open help viewer to check if help appears.

If the following warning appears, turn off the IE enhanced security configuration:

Content from the website listed below is being blocked by the Internet Explorer Enhanced Security Configuration.

<https://docs.microsoft.com>

To turn off the IE enhanced security configuration, perform the following:

1. Open Server Manager.
2. In the left pane, select **Local Server**.

The right pane displays the IE Enhanced Security Configuration option. By default this option is set to On.

3. Click **On**.

The Internet Explorer Enhanced Security Configuration windows appears.

4. Select **Off** under **Administrators**.
5. Select **Off** under **Users**.
6. Click **OK**.

When you view the AB Suite online help in the Information center, an Application Error appears.

Workaround

If the Application Error appears, you must add the Product Support Site to Trusted sites in the Internet security settings of the Internet Explorer.

To add the Product Support Site to Trusted site, perform the following:

1. Open Internet Options.
2. On the **Security** tab, select **Trusted sites**, and then click **Sites**.

The Trusted sites window appears.

3. In the **Add this website to the zone** box, enter the following Product Support Site link:

<https://www.support.unisys.com>

4. Click **Add**, and then click **Close**.
5. Click **OK**.

Uninstalling the AB Suite Developer

You can uninstall the Developer installation from the Programs and Features option in the Control Panel.

Note: *If you want to uninstall Visual Studio, you must first uninstall AB Suite Developer, otherwise fragments of AB Suite Developer might be left after Visual Studio is uninstalled, and might cause problems with future installations.*

To uninstall the AB Suite Developer, perform the following

1. Open **Programs and Features** from **Control Panel**.
2. From the list of installed programs, right-click **Agile Business Suite 8.0 Developer**, and then select **Uninstall**.
3. Right-click from the list, and select **Uninstall**.
4. Click **Yes** when prompted to confirm and continue with the operation. Click **No** if you do not want to uninstall the AB Suite Developer.

Silent Uninstallation

The Developer Installation Package is in the .msi format and supports Silent Uninstallation using the msiexec.exe utility. When the command line argument “/qn” is passed to the utility, the uninstallation of the developer proceeds without Graphical User Interface (GUI). The progress of the uninstallation, indicating success or failure, is written to a log file. The log file includes the status, warnings, and error messages.

Performing Silent Uninstallation of Developer

To uninstall the developer in silent mode, execute the following command from the command prompt:

```
":> msiexec.exe /x "<Developer MSI package path>" /qn
/l*v "<Log file path>"
```

The commands or parameters to execute the AB Suite package are as follows:

Commands or Parameters	Values
msiexec /x	Example: <default>\AB Suite 8.0 Developer\Product Configuration 1\Release 1\DiskImages\Disk1\AB Suite 8.0 Developer.msi
/qn	
/qn+	
/norestart	
/l*v	Example: C:\Temp\AB Suite 8.0.Log

Where,

msiexec is the executable program of the Windows Installer to interpret installation package and uninstall product.

/x switch is used to uninstall the package from the command line.

/qn switch specifies there’s no UI during the process.

/qn+ switch specifies there’s no UI during the process, except for a final dialog box at the end.

/norestart switch specifies no restart of the machine.

/l*v switch is used to create a log file.

Following is an example for silent uninstallation of Developer from the command prompt:

```
msiexec.exe /x "Agile Business Suite 8.0 Developer.msi" /qn /norestart
/l*v "C:\Temp\DeveloperUninstall.log"
```

Uninstalling and Reinstalling AB Suite

To uninstall AB Suite, you must delete all runtime systems. The COM+ settings might be lost when the runtime systems are deleted. Refer to [Uninstall Agile Business Suite Runtime](#) for more information.

A utility, AB Suite COM+ Migrator (ABSCOMMigrator.exe) is provided to save and restore the Pooling and Activation settings after the rebuild of the user systems. You can find the ABSCOMPlusMigrator.exe in the AB Suite Runtime installer, CD Runtime\Windows Runtime\Runtime Utilities.

For an AB Suite Generated COM+ application, both Pooling settings and User Role information can be backed up and restored through this utility. For AB Suite Runtime internal COM+ Settings, only User Role information can be backed up and restored through this utility.

Note: *Ensure that you use ABSCOMMigrator.exe to save and restore the Pooling and Activation settings.*

Backing up and Restoring

Prior to uninstalling AB Suite, you might take a backup of the Pooling settings and User Role information through the AB Suite COM+ Migrator utility. The backup is stored in XML format with a file name specified by you. After reinstalling AB Suite at the desired IC level, you must execute the AB Suite COM+ Migrator utility to restore the settings of the COM+ application.

Each backup file settings include Pooling settings, Activation settings and User Role settings.

1. Following is the list of the Pooling settings for an AB Suite generated COM+ application that can be backed up and restored.
 - Pool Size
 - Lifetime Limit (minutes)
 - Memory Limit (KB)
 - Expiration Timeout (minutes)
 - Call Limit
 - Activation Limit
2. Following is the list of the Activation settings for an AB Suite generated COM+ application that can be backed up and restored.
 - Minimum Pool Size
 - Maximum Pool Size
 - Creation Timeout (ms)
3. User Role settings for an AB Suite runtime application and AB Suite generated COM+ application can be backed up and restored.

Following is the list of the AB Suite Runtime internal COM+ applications that can be backed up and restored.

- Database Manager
- DB Reorganisation
- Debugger Manager
- Deployment Server
- External Call Helper
- Hub Helper
- Hub Transaction Context
- Hub Transaction Co-ordinator
- Print Configuration Manager
- Report Session Manager
- Runtime Manager
- Runtime Versioning
- Security Helper
- Segment Session Manager
- System Privileged


Using AB Suite COM+ Migrator Utility

The AB Suite COM+ Migrator utility enables you to select a link from the following list:

- Backup AB Suite Runtime COM+ Application Settings – Refer to [Backup AB Suite Runtime COM+ Application Settings](#) to back up AB Suite Runtime's internal COM+ application settings.
- Restore AB Suite Runtime COM+ Application Settings – Refer to [Restore AB Suite Runtime COM+ Application Settings](#) to restore AB Suite Runtime internal COM+ application settings.
- Backup AB Suite Generated Application Settings – Refer to [Backup AB Suite Generated Application Settings](#) to back up COM+ application settings for one or more deployed AB Suite applications.
- Restore AB Suite Generated Application Settings – Refer to [Restore AB Suite Generated Application Settings](#) to restore COM+ application settings for a newly re-deployed AB Suite application.

Note:

- *You must install Runtime for the utilities to work as expected.*
- *After executing the AB Suite COM+ Migrator utility, corresponding success or failure message is displayed.*




102222

Backup AB Suite Runtime COM+ Application Settings

This link enables you to back up the User Role settings.

To back up User Role settings, perform the following:

1. Select the path and specify the backup file name (.xml)
2. Click **Backup** to back up the internal COM+ application settings.




Restore AB Suite Runtime COM+ Application Settings

This link enables you to restore the User Role settings to the machine by using the previously backed up settings for an application.

To restore User Role settings, perform the following:

1. Select the path and backup file name (.xml) from where the AB Suite runtime COM+ application settings can be restored.
2. Click **Restore** to restore the AB Suite runtime COM+ application settings.



102226


Backup AB Suite Generated Application Settings

This link enables you to back up Activation settings, Pooling settings, and User Role settings for one or more deployed AB Suite applications on the machine.

1. Select the AB Suite generated application that needs to be backed up from the list of applications available in the AB Suite Generated Applications that can be backed up list box.

Note: The utility lists all the AB Suite generated COM+ applications. You can select the application to be backed up.

2. Select the path and specify the backup file name (.xml)
3. Click **Backup** to back up an AB Suite generated application's settings.




Restore AB Suite Generated Application Settings

This link restores Activation settings, Pooling settings, and User Role settings for a newly re-deployed AB Suite application by using the previously backed up settings.

1. Select the path and backup file name, where the settings of the previously backed up application are stored.
2. Select the AB suite generated applications to be restored from the **AB Suite Generated Applications that can be restored** list box.

Note: A backup file's settings (Pooling settings, Activation settings, and User Role settings) can be applied to multiple AB Suite applications.

3. Click **Restore** to restore the AB Suite generated application's settings.



Using Command Line Options

Use the following command statement to back up and restore the Pooling settings and User Role information.

```
ABSComPlusMigrator.exe [-B|-R] [-S (Com Application name) | -N]
[-X (xml file path)] [-L (log file path)]
```

Note: You can find the *ABSComPlusMigrator.exe* in the *AB Suite Runtime installer, CD Runtime\Windows Runtime\Runtime Utilities*.

Where:

Syntax	Description
-B	To back up the properties of ComApplication
-R	To restore the properties of ComApplication
-S (Com Application name)	To specify the AB Suite generated ComApplication name
-N	To specify AB Suite's Runtime ComApplications.
-X (xml file path)	The name of the Xml File path (Fully qualified path)

Developer Installation

Syntax	Description
-L (log file path)	The name of the log file (Fully qualified path - Optional; if not specified, log file with name ABSCComMigrator.log is created in the location "Data\public\log")
/? or -Help	Lists Help details

Examples for using command line options

This section provides examples on using the command statement.

Examples	Command Statement	Description
To back up ABSuite Generated System's ComApplication, SAMPLECLR	ABSCComPlusMigrator.exe -B -S SAMPLECLR -X "c:\SampleClrBackup.xml" -L "c:\SampleClrBackup.log"	• SAMPLECLR: Generated Com Application name • c:\SampleClrBackup.xml: Fully qualified xml file path. • c:\SampleClrBackup.log: Fully qualified log file path (optional).
To back up ABSuite's Runtime ComApplications	ABSCComPlusMigrator.exe -B -N -X "c:\NGENComApplicationsBackup.xml" -L "c:\NGENComApplicationsBackup.log"	• c:\NGENComApplicationsBackup.xml: Fully qualified xml file path • c:\NGENComApplicationsBackup.log: Fully qualified log file path (optional).
To restore ABSuite Generated System's ComApplication, SAMPLECLR	ABSCComPlusMigrator.exe -R -S SAMPLECLR -X "c:\SampleClrBackup.xml" -L "c:\SampleClrRestore.log"	• SAMPLECLR: Generated Com Application name • c:\SampleClrBackup.xml: Fully qualified xml file path. • c:\SampleClrRestore.log: Fully qualified log file path (optional) Note: One backup file settings (Pooling settings, Activation settings, and User Role settings) can be applied only to one AB Suite application.

Examples	Command Statement	Description
To restore ABSuite's Runtime ComApplications	ABSComPlusMigrator.exe -R -N X"c:\NGENComApplicationsBackup.xml" -L " c:\NGENComApplicationsRestore.log"	- c:\NGENComApplicationsBackup.xml: Fully qualified xml file path. - c:\NGENComApplicationsBackup.xml: Fully qualified xml file path.
To restore properties of ComApplication, SAMPLECLR to ComApplication, CHOCSYSCLR	ABSComPlusMigrator.exe -R -S CHOCSYSCLR -X "c:\SampleClrBackup.xml" -L " c:\ChocsysClrBackup.log"	- CHOCSYSCLR: Com Application name - c:\SampleClrBackup.xml: Fully qualified xml file path - c:\ChocsysClrBackup.log : Fully qualified log file path (optional)

Enabling LargeAddressAware option for Agile Business Suite in Windows

32-bit processes under Windows are limited to address 2 GB memory. However, you can use the 4-gigabyte tuning (4GT) feature on Windows to increase the memory up to 3 GB. You can then use the /LARGEADDRESSAWARE switch to enable AB Suite to use the large address space.

To use the 4GT feature and the /LARGEADDRESSAWARE switch for increasing the memory, perform the following:

1. Enable 4GT using the BCDEdit /set *increaseuserva* command.

You can set the *increaseuserva* option to a value between 2048 (2 GB) and 3072 (3 GB).

2. Open command line.
3. Browse to the folder where devenv.exe is installed.

For example, if you have installed Visual Studio 2019 on C drive, you can locate the devenv.exe in the following location:

C:\Program Files (x86)\Microsoft Visual Studio\2019\Professional\Common7\IDE

4. Type the command editbin /LARGEADDRESSAWARE devenv.exe to enable AB Suite to use the large address space.

Section 4

Developer Configuration

Configure Debugger for Normal Users

This section discusses how to configure AB Suite Debugger so normal users without administrative privileges can debug AB Suite systems. AB Suite internally uses the user group called Debugger Users on the local machine to allow non-administrative users' access to Debugger. The install creates this user group if it does not already exist.

File Permissions for Builder Output and Cache Directories

The following directories need full read and write access by the Debugger Users group. If necessary, you can change the location of the Builder Output and Cache directories through the System Modeler Builder options to use a shared location.

1. Builder Output Directory
2. Cache Directory

The Debugger Users group needs Full Control access on the Builder Output and Cache directories. In order to do this, perform the following:

1. Browse to the location of the Builder Output directory.
2. Right-click the **Builder Output directory**, and select **Properties**. The **Builder Output Properties** dialog box is displayed.
3. Select the **Security** tab, and select the Debugger Users in the Group or user names pane.
4. Select the **Allow Full Control** check box in the Permissions for Debugger users.
5. Click **Apply** and **OK**.

Refer to [Changing Builder Output and Cache Directories](#) for more information on changing the directory locations.

File Permissions for Existing Data Folder

The existing files under the following directories need full read and write permissions for the Debugger Users group.

1. AB Suite 8.0\Data\Private
2. AB Suite 8.0\Data\Public

The Debugger Users group need Read, Write, and Modify access on the existing files under AB Suite 8.0\Data\Private and AB Suite 8.0\Data\Public. To assign the access rights to the debugger group, perform the following:

1. Browse to the location of the Builder Output directory.
2. Right-click the Builder Output directory, and select **Properties**.
The **Builder Output Properties** dialog box is displayed.
3. Select the **Security** tab, and select the Debugger Users in the Group or user names pane.
4. Click **Edit**.
5. Select the **Read, Write, and Modify** check box in the Permissions for Debugger users dialog box.
6. Click **Apply** and **OK**.

Adding New Non-administrative User Access to Debugger

To allow a new non-administrative user access to AB Suite Debugger, an administrator needs to add the user to the Debugger Users group and give appropriate database permissions:

1. Add the new or existing user to the Debugger Users group.
2. Set appropriate database permissions for this user or for all Debugger Users to be able to access the model database. Follow instructions mentioned in the Database Permissions needed subsection.
3. The user can now use Debugger and Debugger Administration applications.

Notes:

- *Debugger users cannot access the Runtime Administration Tool. If Debugger users need a new debugger runtime database, then an Administrator should create their runtime database in the Runtime Administration Tool for them.*
- *Debugger users must add a set of translation libraries specific to the encoding used for EAE OS 2200 when using external classes targeting Kanji data. These libraries are the same as those used by EAE Developer. As the internal code mappings of the Japanese character set are different for the LETS-J code (on OS 2200) and the Shift JIS code (on Windows), you must add the following libraries to the <AB Suite Installation Path>\Bin folder. For example: "C:\Program Files(x86)\Unisys\AB Suite 8.0\Bin" in 64-bit operating system:*
 - *mcutil.dll*
 - *mcletsj.dll*
 - *mbcsconv.dll*

- *eudcserv.dll AB Suite 8.0 does not support 32-bit operating systems.*

Changing Builder Output and Cache Directories

The Builder Output and Cache Directory Locations should be in a shared directory location. This ensures that all normal Debugger users without administrative privileges can access the model database.

To change the Builder Output and Cache directories, perform the following:

1. Log on as an administrator.
2. Launch **Microsoft Visual Studio 2019**.
3. Select **Options** from the Tools menu.
4. Navigate to System Modeler, and then Builder.
5. Change the Location of Cache and Builder Output to a shared directory location that all users can access.

Database Permissions Needed

Create new model databases (optional)

This permission is required if a debugger user without administrative rights wishes to use AB Suite to create new models.

1. Log on as an administrator of the computer.
2. Launch **Microsoft SQL Server Management Studio**.
3. Navigate to Security and then Logins.
4. Add the debugger user as a new login. You can either add the individual user or the Debugger Users group. Adding the Debugger Users group is recommended if all your users can access the same databases.
5. Right-click or double-click to view the properties on the added user.
6. Choose Server roles and check dbcreator. This allows the user to create new databases when creating a new AB Suite model.

Accessing existing model databases (required)

This permission is required for debugger users without administrative rights who want to use existing AB Suite model databases.

1. Log on as an administrator to the computer.
2. Launch **Microsoft SQL Server Management Studio**.
3. Navigate to Security and then Logins.
4. Right-click on the Login node and select **New Login**. Add the debugger user as a

new login. You can either add the individual user or the Debugger Users group. Adding the Debugger Users group is recommended if all your users can access the same databases.

5. Ensure Windows authentication is selected.
6. Choose User Mapping and select the model database that the user needs access to.

Runtime databases for debugging

Without Administrative rights, Debugger Users cannot access the Runtime Administration Tool to create and delete runtime databases. If your Debugger users need a new debugger runtime database, then an Administrator should create their runtime database in the Administration tool for them.

Configure Debugger for Remote Desktop Users

To configure Debugger for Remote Desktop users, follow the same procedure as required for normal users, but the configuration properties for each remote user should be different. Since, each remote user needs to create their own configuration in the model with unique property values. Ensure to specify unique values for the Segment configuration properties; COM Prog ID, Alternate Name, and DB Schema Name.

Section 5

Client Environment Installation

This section describes how to install the Agile Business Suite Client Environment.

Required System Software

This section describes the software required for Component Enabler and Client Framework. Depending on how you use Component Enabler and Client Framework, you might require some or all of the following components:

- Windows 10 Professional (x64) v1909, Windows Server 2019 (LTSC) Standard, Datacenter, Windows 10 Enterprise (x64) November 2019 v1909.
- Agile Business Suite Developer and Builder
- Web server
- Remote Access server
- Agile Business Suite Runtime

The system requirements vary, depending on how you plan to access the Client Environment applications. Any differences in system requirements are noted for each component. There might also be additional requirements for individual components, in which case they are specified in the relevant section.

Generation Workstation

The development and generation workstation for Component Enabler requires the following software:

- Agile Business Suite Developer and Builder, to generate classes from the system definitions stored in the Developer Model database.
- Microsoft Visual Studio 2019 – enhance the generated applications for .NET, such as ASP.NET Web Forms, ASP.NET Web Services and the VB.NET Client).
- A Development Environment of choice, if you are developing your own applications to access the Component Enabler client interface.

You require one of the following to use the Java Generate Environment:

- Oracle Java[®] SE 11 or later
- OpenJDK 11 or later

Client Environment Installation

For the Microsoft .NET based Generate Environment:

- Microsoft .NET Framework 4.8.

When generating Java based applications, you need the Java Software Development Kit v1.6 or later. When generating for Microsoft .NET based applications, you need the C# compiler installed on the machine.

The developer workstation for the Client Framework requires the following software:

- Agile Business Suite Developer and Builder
- The development environment for the technology of choice; for example, Microsoft Visual Studio 2019 to develop applications by using technologies, such as WPF/XAML, ASP.NET MVC (Model-View-Controller), Windows Communication Foundation (WCF), and Windows Store Apps
- Microsoft .NET Framework 4.8

Note: *If you are developing Windows Store Apps by using Client Framework, you must install AB Suite Developer on Windows 11 or later operating system.*

Client Workstation

The Component Enabler client workstation is the workstation through which users access Component Enabler applications. You need the following software on your client workstation:

Notes:

- *These applications do not require the JDK or the C# compiler on the client workstation.*
- *For Java applications that use Component Enabler, you need a Java Virtual Machine, such as the Oracle Java SE 11 or later.*
- For applications that use the Component Enabler for .NET interface, you need:
 - The Microsoft .NET Framework 4.8 or later.You do not need a Web browser.
- When running the Presentation Client as a standalone application, or the JSP Client, you need:
 - An operating system with TCP/IP services installed, for example, Windows 10 Enterprise (x64) Professional, Enterprise (x64) October 2018 Update or Mac OS X.
 - A Java 1.6 or higher Virtual Machine (JVM), such as the one supplied by Oracle.
- When running the Presentation Client from a Web browser, you need:
 - An operating system with TCP/IP services installed; for example, Windows 10 Enterprise (x64), Professional (x64) October 2018 Update or Mac OS X.
 - One of the following qualified browsers:
 - Microsoft Internet Explorer 11.0 or later
 - FireFox or later

Safari (for MAC OS X)

- Java version 1.6 or later, compatible plug-in.

Note: *These applications do not require the JDK on the client workstation.*

- For applications that use scripted pages on a Web server, you need an operating system with TCP/IP services installed; for example, Windows 10 Enterprise (x64) Professional, Enterprise (x64) October 2018 or UNIX®.

Remote Access Server

To communicate with a Component Enabler client, you need the following software on the server for the host system:

- Agile Business Suite Runtime
- TCP/IP
- Remote Access Server software

Note: *After the Remote Access server software is installed, you need to create Component Enabler Views before using the Remote Access servers to access the system. Refer to the Agile Business Suite Runtime Administration Guide for your host platform for more information.*

The Client Framework client workstation might be an end-user workstation or a server machine. A new connection mechanism, Access Layer API, is available in the Client Framework for connecting a client to the runtime system. The Access Layer API allows the client application to interact with the deployed AB Suite system and is exposed through Direct and Remote connection.

For direct connections, the client workstation requires the following software:

- .NET Framework 4.8
- Access Layer API assemblies
- Data Models assembly for an application
- Application specific components. For example,
 - Data View Models and Views assemblies for a WPF Client application
 - Any dependent software required by the client technology that was used to develop the client application such as custom WPF Toolkit

Client Framework WCF Gateway Services

To remotely access the runtime system for Client Framework applications, the following AB Suite WCF gateway services are installed:

- AB Suite 8.0 Client Framework (WCF) FileStore Gateway – Allows Client Framework clients to retrieve or store files, such as images.
- AB Suite 8.0 Client Framework (WCF) Gateway – Allows Client Framework to access an AB Suite System over TCP/IP.

These services are installed when you install the AB Suite Runtime for Windows, and client applications can use them to interact with the deployed AB Suite runtime system.

For Developers, the Client Framework WCF Gateway Host application is also installed with the AB Suite Developer for Windows software. This is a WCF Service hosting application that can be used to test the WCF Gateway services on a machine where the AB Suite Runtime software is not installed. Refer to the *Agile Business Suite Developer User Guide* for more information on the WCF Gateway Host.

WCF follows a client-server model to establish communication between applications. The AB Suite WCF gateway can be

- Self-hosted in any managed .NET application
- Hosted as a Windows service
- Hosted in different versions of Internet Information Services (IIS)

Refer to the *MSDN documentation* for more information on hosting and consuming WCF services.

The remote Access Layer API uses .Net Portable Library assemblies. It can be used wherever portable libraries are required. For example, Windows 8 Store Apps, Silverlight , and Windows Phone 8 clients.

To enable Client Framework applications to connect to the runtime system remotely, the client workstation requires the following:

- .Net Framework Portable subset
- Access Layer API Remote assemblies
- .Net Portable DataModels for the application
- Application specific components. For example,
 - DataViewModels and Views assemblies for client application.
 - Any dependent software required by the client technology that was used to develop the client application.
- The WCF Gateway server requires the following:
 - .Net Framework 4.8 or later
 - Access Layer API assemblies
 - .Net DataModels for an application

To configure the WCF Gateway, you must modify its associated configuration file, `Unisys.ABSuite.AccessLayer.GatewayServiceLibrary.dll.config`, which is installed in the Bin folder of the AB Suite installation directory.

Refer to the *MSDN documentation* for more information on configuring WCF Services and the options you can specify in the configuration file.

Client Framework Custom Service Libraries

If you have developed a custom WCF Service by using the Client Framework WCF Service technology option, you can install the associated WCF Hosting application as a Windows Service to host your Service Library.

You can install the associated WCF Hosting application as a Windows Service by running the following command from the command prompt:

```
InstallUtil <SegmentName>.<FolderName>Gateway.exe
```

To run the WCF Service with a specified user name and password, you must run the following command from the command prompt:

```
InstallUtil /user=<username> /password=<myPassword>  
<SegmentName>.<FolderName>Gateway.exe
```

Notes:

- You can run the WCF Service by using the Application User account. Alternatively, you can use a credential that has similar rights as the Application User.
- If you do not specify a user name and password, the WCF service runs as a local service.

Refer to the *Agile Business Suite Developer User Guide* for more information on creating a custom service library.

To configure the custom service library for your WCF Hosting application, you must modify the necessary tags in the app.config file. The app.config file is created on the generation of the service library project.

When you host this gateway you can find the app.config file in the Solution Explorer window under WcfServiceLibrary project.

Refer to the *MSDN documentation* for more information on configuring the WCF gateway.

Minimum Hardware Requirements

This section describes the minimum recommended hardware requirements for installing Agile Business Suite Client Environment.

Hardware	Runtime
Processor	4 GB RAM
Memory	
Disk space	200 GB
Monitor	LCD

Installing the Client Environment

To install Client Environment you must click Client Environment on the Unisys Installation Interface.

This displays the Client Environment interface. Note that the following installation options are selectable for installation on a development machine or on a client machine of the user.

From this interface, you can select the Client Environment that you want to install by clicking the appropriate button. The options are:

- Winform – installs either Winform 32-bit or Winform 64-bit software on a client machine depending on the operating system. You do not need to install this component if you have already installed the Development Environment, as the Winform container is included in that installation.
- Component Enabler – installs the Component Enabler software on a development machine.
- Presentation Client – installs the Presentation Client on a client machine. You do not need to install this component if you have already installed Component Enabler, as the Presentation Client is included in that installation.
- Business Integrator – installs the Business Integrator and associated product information on a development machine for generation with Component Enabler.
- Client Framework – installs the standalone Client Framework on a client machine. You do not need to install this component if you have already installed the Development Environment, as the Client Framework software is included in that installation.

Installing Winform

Before you install the Winform software, you must install the following software:

- Windows 10 Professional (x64) v1909 Update, Windows Server 2019 (LTSC) Standard, Datacenter, Windows 10 Enterprise (x64) v1909 Update
- .NET Framework 4.8

You must also have administrative privileges on the machine on which you want to install Winforms, and 5Mb of free disk space.

Note: *For the Winform client machines to communicate with the runtime server, the usercodes of the client machines must be known on the server. This is accomplished when a user logs in by using a domain usercode/password, and that domain is trusted on the server. The Winform client machines cannot communicate with the runtime server if they are across non-trusted domains.*

You can install Winform (32-bit) or (64-bit) software on a client machine. You do not need to install this component if you have already installed the Development Environment, as the Winform container is included in that installation.

Click **Winform (32-bit)** or **Winform (64-bit)** to begin the installation. The Installation wizard appears and a number of checks are carried out on the system to ensure it has the correct underlying system software to complete a satisfactory installation. If the checks identify that a copy of Developer is installed on the machine, the Winform installation does not proceed, as the Developer installation includes the Winform software, which is required for the debugger functionality.

Note: *If two instances of the installation wizard appear, close one instance.*

If the checks indicate that the Winform software is already installed on the machine as a separate instance, the Repair Remove dialog box appears.

If the checks are successful, a welcome dialog box appears, followed by a license dialog box. Click **Yes** on the license dialog box, if you want to accept the conditions and continue with the installation.

You can then select the target drive and directory for the installation, if you do not want to accept the default installation location.

Note: *If an installation of Agile Business Suite Runtime exists on the target machine, the destination dialog is skipped, as the Winform software must be installed in the same location as the existing Runtime components.*

When you have entered the location for the target drive and directory, or accepted the default location for the installation, click **Next** to display the Start Copying Files dialog box. This allows you to review the installation settings before completing the installation. This screen displays components that are selected and the installation directory. If you are satisfied with the settings, click **Next** to proceed with the installation. You can click **Back** to make changes, if any.

At the completion of installation, the Installation Complete Screen appears. This screen allows you to view the readme file. If you do not want to view the readme file, clear the check box. Click **Finish** to complete the installation.

Configuring Winform

Before running applications, you must edit a configuration file named config.xml. This is an xml file that contains configuration information to enable the Winform clients to find and connect to the application component. This file is automatically created by the generation of the system. The administrator might have already modified this configuration file in the installation package. Check with your administrator before proceeding.

A default copy of config.xml file is located at <AB Suite installation folder>\Unisys\<AB Suite>\Bin.

Alternatively, a pre-configured version of this Winform configuration file, named ispec.xml is automatically generated each time a system is built with Builder. This file is located in the systems installation Bin folder.

For example:

C:\Sample\Release_Windows\SAMPLE\Core\Bin

An ispec.xml file is created for each deployment folder if you set the *Deploy Winform User Interface* property to True and if you customize the *Final Location* and *Download URI* properties.

The ispec.xml file is created and is available in the Builder Output folder. You can directly use this ispec.xml file as the two properties *DownloadServerURI* and *LocalDownloadDirectory* are already configured.

To locate the ispec.xml file:

1. Locate the Packages directory in the Builder Output folder, in the location <Builder Output Path>\<System Name>\<GUID ID>\Packages.
2. If you have multiple folders in the model, then you will find similar folders inside the Packages directory.
3. Locate the particular Winform folder and open the folder.
4. You will find the ispec.xml file generated for this folder.

The following entries might need to be edited:

1. <system name> should be set to a string with the name of the system. This name appears on the title bar of the Winform window. For example, <system name = "Sample">
2. <startupSystem name> should be set to the same string as <system name>. Note that you can have multiple <system name> sections in the config.xml file. This <startupSystem name> entry specifies which system is started when you first open the Winform Container. For example, <startupSystem name="Sample">
3. <componentName> should be set to the name of the COM Program ID that the system was generated with. Contact your administrator for this value. For example, <componentName>SAMPLE</componentName>. This name is case sensitive and must correspond to the case of the actual name of the COM Prog ID.
4. <runtimeServer> must contain the machine name where the runtime system was deployed and installed. Contact your administrator for this value. Use "localhost" if you generated a test system to your own machine.
5. <downloadServerURI> is where the generated Winform dlls have been copied. For example, <downloadServerURI>http://192.234.333.23/WinFormsDownload/SAMPLE</downloadServerURI>
or <downloadServerURI>file:///C:\Sample\Release\SAMPLE\Interfaces\WinForms\Bin
6. <GIWCompatibleBehaviour> can be set to true or false. If set to true, then the behavior of some GUI controls are backwards compatible with a previously used client product called GIW (Graphical Interface Workbench). The specific GIW behavior includes the following:
 - Push Buttons: When a push button is pressed, the values associated with all other push buttons on the form is cleared, so that only the value for the pressed push button is sent to the host.
 - Radio Buttons: In a radio button group, if no button in the group is set (a default

button has not been defined and none of the button values match the value sent from the host) then the first button in the group is set.

Language numbers are added automatically and do not need to be included as part of this entry.

Configuring Winform for ROC

If you want to connect to the Report Output Control System (ROC) from another application using the Roc command, you must first configure the Winforms client to support switching to the ROC system. To do this, add the following XML to the end of the config.xml file:

```
<system name="ROC18">
  <componentName>ROC18</componentName>
  <runtimeServer>localhost</runtimeServer>
  <downloadServerURI>
file://C:\ROC\Release\ROC18\Interfaces\WinForms\Bin
  </downloadServerURI>
  <localDownloadDirectory>.\</localDownloadDirectory>
  <defaultImageType>.jpg</defaultImageType>
  <defaultImageSubDirectory>images</defaultImageSubDirectory>
  <defaultListType>.xml</defaultListType>
  <defaultListSubDirectory>lists</defaultListSubDirectory>
  <disableConsole>>false</disableConsole>
  <GIWCompatibleBehaviour>>false</GIWCompatibleBehaviour>
  <enableLogging>>true</enableLogging>
  <logFile>.\client.log</logFile>
</system>
```

Note: For 64-bit, you need to modify the <downloadServerURI> entry with the following:

```
<downloadServerURI>
file://C:\ROC\Release\ROC18\Interfaces\WinForms\Bin64
</downloadServerURI>
```

Configuring Winform for Cloned Reports

The default Winform configuration file that is used to generate during the build (that is, "ispec.xml" in Core\Bin folder) is based upon the list of reports available in the development model at build time. The creation of report clones using another application (namely, Deployment Package Manager) is a completely separate activity, which is performed in the deployment environment on the target machine. This means that the building of the Winform configuration file does not know anything about which report clones might or might not have been deployed.

However, you can still configure the Winform configuration file to display the cloned reports in Winform in the following way:

Open the Winform configuration file in a text editor and search for the <reports> tag. You can add the following details:

```
<report name="CLONED_REPORT_NAME"  
description="CLONED_REPORT_DESCRIPTION" />
```


Installing Component Enabler

Before you install the Component Enabler software and any of the generators, you need to install some of the following software depending on your requirements:


- Agile Business Suite Developer and Builder
- Oracle Java SE 11 or OpenJDK 11 or later. Java 64-bit is also supported.
- Microsoft .NET Framework 4.8 or later
- Microsoft Visual C++ Redistributable for Visual Studio 2019. This requirement is a must for VB.Net Client only.

Note: *Agile Business Suite Component Enabler cannot be installed on a machine on which a previous version of Enterprise Application Component Enabler exists.*

You can also run the AB Ready tool to check the status of the prerequisite software for Component Enabler installation.



104070



Click **Component Enabler** to begin the installation. The Installation wizard appears and a number of checks are carried out on the system to ensure it has the correct underlying system software to complete a satisfactory installation.

Note: If two instances of the installation wizard appear, close one instance.

If the checks are successful, a welcome dialog box is displayed, followed by a license dialog box. Click **Accept** on the license dialog box, if you wish to continue with the installation.

Note: It is recommended to restart Visual Studio after installing Component Enabler, if Visual Studio was open during the installation of Component Enabler. This must be done, for Visual Studio to recognize the environmental variable settings and to avoid compilation errors during the generation of bundle for presentation client.

Custom Setup

When you accept the license agreement the Custom Setup dialog box is displayed, which provides the following options:

- Component Enabler for Java
- CE Generate Environment for .NET Framework
 - ASP.NET Web Forms Generator
 - ASP.NET Web Services Generator
 - VB.NET Forms Generator

- JSP Generator
- ePortal Generator
- CE Runtime for .NET Framework
- Generator Customization Kit

Component Enabler for Java

If you select **Component Enabler for Java** during your Component Enabler installation, the Component Enabler Runtime and Generate environment for Java are installed as part of the setup program.

Component Enabler Generate environment requires that Java JDK version 11 or later be installed on the target machine. When you select Component Enabler and Java JDK version 11 or later is not detected, a message box will prompt you to install Java JDK 11 or later before selecting this feature.

The Component Enabler installation also installs the Presentation Client software. It is recommended that you must have JDK 11 or later to continue the installation.

Note: *The version of JRE must be greater than or equal to JDK. Otherwise, the installer aborts the installation and displays a message.*

CE Generate for .NET Framework

If you select the **CE Generate for .NET Framework** during your Component Enabler installation, the CE Generate for .NET Framework is installed as part of the setup program.

This installs the following files:

- [CERoot]\bin\CEGenerateDotNET.dll
- [CERoot]\bin\CEGeneratorDotNETResources.xml
- [CERoot]\bin\CEGenerateDotNET.xml
- [CERoot]\ReadmeCEGenerateDotNET.htm

The installation registers the CEGenerateDotNET.dll with COM and in the Global Assembly Cache as follows:

```
regasm [CERoot]\CEGenerateDotNET.dll  
/tlb:[CERoot]\CEGenerateDotNET.tlb  
gacutil -i [CERoot]\CEGenerateDotNET.dll
```

The CEGenerateDotNET.dll can be unregistered as follows:

```
gacutil /u CEGenerateDotNET,PublicKeyToken=d75f28b512e9147c  
regasm [CERoot]\CEGenerateDotNET.dll /unregister
```

This feature requires that .NET Framework 4.8 be installed on the target machine. When you select this feature and .NET Framework 4.8 is not detected, a message box will prompt you to install .NET Framework 4.8 before selecting this feature.

ASP.NET Web Forms Generator

If you select the **ASP.NET Web Forms Generator** during your Component Enabler installation, the ASP.NET Web Forms Generator is installed as part of the setup program.

When you select this feature and you have not selected either CE Runtime for .NET Framework or CE Generate for .NET Framework, a message box will prompt you to install one of those feature options.

The ASP.NET Generator in the AB Suite 8.0 Release includes support for AJAX technology.

In order to install and run the generator you need to have the following additional system software installed above the base Component Enabler software requirements.

- Microsoft .NET Framework 4.8
- Microsoft Visual Studio (optional).

This is only required on the generation workstation if you wish to modify the generated project file in order to perform customization prior to compiling the files as an ASP.NET Web Forms application

- Microsoft Internet Information Services 10.0 or later (optional).

This is only required on the generation workstation if you wish to deploy and test the ASP.NET Web Forms Application locally.

The Web Server

- Microsoft .NET Framework 4.8
- Microsoft Internet Information Services 10.0 or later

The Application Server

TCP/IP capability is required on the Enterprise Application System with the Remote Access server software and the web server.

Installation Structure

The installation creates a new subdirectory called ASP.NET Generator in the installed Component Enabler Directory (for example, ..\ASP.NET Generator).

The C# version of the ASP.NET Web Forms Generator is a dll called GenerateFormASPdotNET.dll, which is copied into the Component Enabler "Bin" directory for use by the CE .NET Generate environment.

The ASP.NET Web Forms Generator installation directory includes the following sub directories:

- Bin – Contains two dll's called UniCombo.dll and UniMenu.dll. They are used at runtime to provide support for combo-boxes and a right-click context menu in the ASP.NET Web Forms.
- Common – Contains infrastructure files that are common to the entire application.

- Images – Contains a default image called blank.gif, which is used when the requested image file is not found at runtime.
- Lang – Contains infrastructure files that can be customized for each language of an application.
- Utilities\Setup – Contains sample scripts that can be used to compile the generated files and establish the Virtual directory for the ASP.NET application. The SetupASPNet.vbs script creates a specified Virtual directory, a physical directory and copy the required files across from the installed ASP.NET Web Forms Generator directories into the correct locations.

Configuration

Specify <Install Directory>\Bin\GenerateFormASPdotNET.dll as the User Defined View Generator in the CE Folder properties.

ASP.NET Web Services Generator

If you select the **ASP.NET Web Services Generator** during your Component Enabler installation, the ASP.NET Web Services Generator is installed as part of the setup program.

When you select this feature and you have not selected either CE Runtime for .NET Framework or CE Generate for .NET Framework, a message box will prompt you to install one of those feature options.

In order to install and run the generator, you need to have the following additional system software installed above the base Component Enabler software requirements.

The Generation Workstation

- Microsoft .NET Framework 4.8
- Microsoft Visual Studio (optional)

This is only required on the generation workstation if you wish to modify the generated project file in order to perform customization prior to compiling the files as a Web Services.

- Microsoft Internet Information Services 10.0 or later (optional)

This is only required on the generation workstation if you wish to deploy and test the Web Services locally.

The Web Server

- Microsoft .NET Framework 4.8
- Microsoft Internet Information Services 10.0 or later

The Application Server

TCP/IP capability is required on the System with the Remote Access server software, and the web server.

Installation Structure

The installation creates a new subdirectory called Web Services .NET Generator in the installed Component Enabler Directory (for example, ..\Web Services .NET Generator).

The C# version of the Web Services .NET Generator is a dll called GenerateWSdotNET.dll. This dll file is copied into the Component Enabler Bin directory for use by the CE .NET Generate environment.

The Web Services .NET Generator installation directory includes the following sub directories:

- common\views – contains infrastructure files such as error checking files, a configuration XML file and a compiler batch file.
- utilities\BundleViewSetp – contains Visual Basic script files.
- utilities\discoveryTool – contains a Web Service Discovery tool for testing generated Web Services.

Configuration

Specify <Install Directory>\Bin\GenerateWSdotNET.dll as the User Defined View Generator in the CE Folder properties.

VB.NET Forms Generator

If you select the **VB.NET Forms Generator** during your Component Enabler installation, the VB.NET Forms Generator is installed as part of the setup program.

When you select this feature and you have not selected CE Runtime for .NET Framework and CE Generate for .NET Framework, a message box will prompt you to install one of those feature options.

JSP Generator

If you select JSP Generator during your Component Enabler installation, the JSP Generator is installed as part of the setup program. When you select this feature, the CE Generate for .NET Framework is installed.

In order to install and run the JSP Generator you must have the following additional system software installed above the base Component Enabler software requirements.

- Oracle JDK 11 or OpenJDK 11
Note: *JDK is required for Presentation Client and JSP Client generation.*
- Java based IDE. For example, Eclipse

This is only required on the generation workstation if you wish to modify the generated jsp files in order to perform customization prior to compiling the files as a JSP Web application.

- Apache Tomcat 6.0 or 7.0 (apache-tomcat-6.0.26-windows-x86)

This is required if you wish to run the JSP Web application.

Installation Structure

The installation creates a new subdirectory, JSP Generator in the installed Component Enabler Directory (for example, ..\JSP Generator).

The JSP Client Generator is a .NET assembly called GenerateFormJSP.dll, which is copied into the Component Enabler Bin directory for use by the CE .NET Generate environment.

The JSP Client Generator installation directory includes the following sub directories:

- Common – Contains infrastructure files that are common to the entire JSP application.
- Lang – Contains infrastructure files that can be customized for each language of a JSP application.
- Utilities\Setup – Contains scripts that establish the virtual directory for the JSP application. The sample script, SetupJSP.vbs is a wizard that guides the user through the steps for setting up the folder structure for the Web Application, copies all necessary infrastructure files into the Tomcat_home\webapps directory. The ce.properties file, which is located at, TOMCAT_HOME\webapps\<application_name>\WEB_INF\classes is updated with values for the following properties.

- Application Name
- Bundle Name
- Package Prefix

You must update the following values in the ce.properties file manually.

- Username
- Password
- View name
- Host name
- Host port

Configuration

To use the JSP Client Generator, you must specify GenerateFormJSP.dll as the User Defined View Generator in the CE Bundle Folder properties of the System Modeler or EAE Developer.

CE Runtime for .NET Framework

If you select the **CE Runtime for .NET Framework** during your Component Enabler installation, the CE Runtime for .NET Framework is installed as part of the setup program.

This feature requires that .NET Framework 4.8 be installed on the target machine. When you select this feature and .NET Framework 4.8 is not detected, a message box will prompt you to install .NET Framework 4.8 before selecting this feature.

Generator Customization Kit

If you select the **Generator Customization Kit** during your Component Enabler installation, you are prompted for a valid password. The password is the software key for the Client Generator Customization Kit, provided in the key document that accompanies the Component Enabler Software. Once you supply this password, the Generator Customization Kit is installed as part of the setup program. It is installed within the Component Enabler directory structure in its own folder.

Completing the installation

When you have selected the components that you want to install, perform the following:

1. Click **Next**.

The Java Folder screen appears.

2. In the **Java Folder** screen, you can either set Java path to the default Java folder or click **Change** to set a different location.

You require a Java version 11 or later of Oracle Java SE or OpenJDK. If the required Java version is unavailable, an error message appears.

Note: You must download the OpenJDK files and extract them in the 64-bit <Program Files\OpenJDK> folder.

3. Click **Next** to display the Ready to Install the Program Screen.
4. Click **Install** to proceed with the installation, otherwise click **Back** to make changes.

After the installation has finished, the Installation Complete Screen is displayed. Click **Finish** to complete the installation.

Oracle JRE Installation and Configuration

The Oracle JRE v1.6 or later is used in Builder to generate Component Enabler files. It can also be used with clients that rely on the COM/Java bridging support which the Microsoft JVM has previously provided (for example, VB Clients, Active Server Pages, etc.). This functionality is now being supported by the ActiveX Bridge feature that is available in the Oracle JRE v1.6 or later. The following information describes the procedure required to setup the Component Enabler Development and Runtime environments for use with the Oracle JRE ActiveX bridge functionality.

Development Environment Generate Setup (Oracle JRE - ActiveX Bridge)

To configure your Development environment for use with the Oracle JRE, perform the following:

1. Download the Oracle Java from the Oracle Java Web Site at <https://www.oracle.com/java/technologies/javase-java-archive-javase6-downloads.html>.
2. Install Java, that is, both JDK and JRE.
3. If you have not already done so, install Component Enabler from the installer.
4. Depending on your environment configuration, you might need to adjust the necessary levels of security for running the Component Enabler Generator functionality through the Java Plugin. The Java policy file is called "java.policy" and is located in the <JRE_HOME>\lib\security directory.

For example:

```
C:\Program Files\Java\j2re1.6.0\lib\security\java.policy
```

In order to provide the Component Enabler generation environment with access to the required machine resources through the Java Plug-in, the following setting is automatically included by the Component Enabler Installation program. In most cases, you will not need to adjust it. However, if it is removed or the policy file is replaced at any stage, you might see security violation errors appearing in the Java Console, and the generate is not completed successfully. If this occurs, you must add the following permission manually.

```
grant codeBase "file:C:\\NGEN_CE\\lib\\*" {  
    permission java.security.AllPermission;;  
}
```

While this requires less effort than setting individual permissions, to achieve the necessary results, it does increase the security risk on the machine. It means that a Java application in that codeBase specification will have unrestricted access to the machine resources. When dealing with Unisys supplied components this should not be a problem. However, you might wish to incorporate more stringent security than the above permission provides. If so, you can remove the AllPermissions setting and ensure that the following are the minimum permissions that are set in order for the application to work correctly.

Note: In case of Java 32-bit, the Java.policy file is updated automatically during the installation of the Component Enabler. If you have Java 64-bit installed, then perform the instructions as mentioned above.

- To create the Generate.Log file in the C:\Temp directory, add the following permission

```
permission java.io.FilePermission  
    "c:\\temp\\GENERATE.LOG", "write";
```

- To create the output files from the generate (for example, IspecModel classes, ASP Forms, VB Forms) permissions are set by default for the directory "C:\NGEN_CE\Classes". This directory must match the directory specified in Developer for the output directory of the Component Enabler bundle. For example, if you have specified C:\NGEN_CE\Classes in the Application Bundle details, then the file permission should be:

```
permission java.io.FilePermission  
    "C:\\NGEN_CE\\classes\\-", "read,write";
```

5. Before you can generate Component Enabler files from Builder, the Java Plug-In Runtime Parameters need to include the CLASSPATH for the JAR files required by the generate process. Add the classpath settings as a Java Runtime Parameter in

the Advanced Tab of the Java Plug-In Control Panel. This allows the ActiveX bridge software to find the Jar files required for the Generate.

For example:

```
-cpc:\NGEN_CE\classes;c:\NGEN_CE\lib\generate.jar;  
c:\NGEN_CE\lib\lincapplet.jar;c:\NGEN_CE\lib\lincviewer.jar;  
c:\NGEN_CE\lib\ASPGenerator.jar;c:\NGEN_CE\lib\WSGenerator.jar;  
c:\NGEN_CE\lib\VBGenerator.jar;
```

Note: *If you have not installed all the optional generators, ASP, WS, or VB it is recommended to still add these paths on completion of the initial installation to avoid possible future errors if the generators are installed at a later date.*

WorkStation Client Setup (Oracle JRE with ActiveX Bridge)

To configure your workstation client runtime environment to use the Oracle ActiveX bridge instead of the Microsoft JVM COM-Java support, perform the following:

1. In order to run the generated VB client or any other COM-based client that you have developed, you need to register the LINCEnvironment class.

Unlike previous releases, the ActiveX bridge binaries for custom Java generators is not copied to the target machine during the installation of Component Enabler. Instead these files are placed inside a folder, **axbridge**, in the Component Enabler folder of the Developer installer.

The installer of Component Enabler gives priority to Java 64-bit. If the machine has both Java 32-bit and 64-bit installed, Component Enabler gets bound to Java 64-bit.

2. In order to deploy the Component Enabler client application to another machine, copy the axbridge folder and its contents to the <JRE_HOME> in the target machine.

This step also copies the LINCApplet.Jar file that contains the LINCEnvironment class into the corresponding "lib" directory.

For example:

```
<JRE_HOME>\axbridge\lib\LincApplet.jar
```

Notes:

- *To determine whether you have Java 32-bit or 64-bit installed. You can check the registry key as follows:*

For example:

If you have Java 32-bit installed in 32-bit environment:

*HKEY_LOCAL_MACHINE\SOFTWARE\JavaSoft\Java Runtime Environment
and*

HKEY_LOCAL_MACHINE\SOFTWARE\JavaSoft\Java Development Kit

If you have Java 32-bit installed in 64-bit environment:

*HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\
JavaSoft\Java Runtime Environment*

and

```
HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\  
JavaSoft\Java Development Kit
```

If you have Java 64-bit installed in 64-bit environment:

```
HKEY_LOCAL_MACHINE\SOFTWARE\JavaSoft\Java Runtime Environment  
and
```

```
HKEY_LOCAL_MACHINE\SOFTWARE\JavaSoft\Java Development Kit
```

- Determine the JRE home.

For example:

For Java 1.6 32-bit in a 64-bit environment:

```
C:\Program Files (x86)\Java\jre6
```

For Java 1.8 64-bit in a 64-bit environment:

```
C:\Program Files\Java\JRE1.8.0_92
```

3. Once the dll is in place on the client machine, run the command prompt as Administrator, execute the regsvr32 command to register the dll.

For example:

In a 32-bit machine:

```
C:\Windows\System32\regsvr32.exe /s  
"<JRE_HOME>\axbridge\bin\LINCEnvironment.dll"
```

and

```
C:\Windows\System32\regsvr32.exe /s  
"<JRE_HOME>\axbridge\bin\GenerateProxyLDA.dll"
```

In a 64-bit machine:

```
C:\Windows\SysWOW64\regsvr32.exe /s  
"<JRE_HOME>\axbridge\bin\LINCEnvironment.dll"
```

and

```
C:\Windows\SysWOW64\regsvr32.exe /s  
"<JRE_HOME>\axbridge\bin\GenerateProxyLDA.dll"
```

4. In your application, specify the class to be used when creating the LINCEnvironment object. For a generated VB application, modify the Class_Initialize() subroutine of the EAEnvironment.cls module, in order to select the appropriate method for creating the LINCEnvironment object. Use the following line of code for the Oracle ActiveX bridge environment:

```
Set mobjLinc = CreateObject("LINCEnvironment.Bean.1")  
' Oracle JVM with ActiveX bridge
```

Ensure the alternative line of code for using the Microsoft JVM is commented out.

5. Add the classpath settings as a Java Runtime Parameter in the Advanced Tab of the Java Plug-In Control Panel. This allows the ActiveX bridge software to find the Component Enabler IspecModel classes that have been deployed to the workstation.

For example:

```
-cp c:\NGEN_CE\classes;
```

6. Update the Java policy file. Depending on your environment configuration, you might need to adjust the necessary levels of security for running the VB Client using the ActiveX bridge through the Java Plugin. The Java policy file is called "java.policy" and is located in the <JRE_HOME>\lib\security directory.

For example:

```
C:\Program Files\Java\j2re1.6.0\lib\security\java.policy
```

7. The following settings might need to be added to provide the Component Enabler Runtime environment with access to the required machine resources. If they are omitted, you might see security violation errors appearing in the Java Console, and the client application will not run successfully.

- Socket Permission – This grants access to the machine that hosts your Agile Business Suite Runtime application:

For example:

```
permission java.net.SocketPermission "HostComputer",
"connect,resolve"; // Where Host Computer
is the computer name on the Domain or the IP Address.
```

- Runtime Permission – The following two entries might be necessary when running the generated VB client application

```
permission java.lang.RuntimePermission "modifyThreadGroup";
permission java.lang.RuntimePermission "modifyThread";
```

- File Permission – If you have set up the Client application to perform logging using the Component Enabler Log object, you need to specify a File Permission giving the name and location of the log file.

For example:

```
permission java.io.FilePermission
"c:\\temp\\VBClient.log", "write";
```

Note: An alternative to setting individual permissions for either the development or runtime environment, would be to set the AllPermission permission on the Component Enabler codeBase directory.

For example:

```
grant codeBase "file:C:\\NGEN_CE\\lib\\*" {
permission java.security.AllPermission;
};
```

While this requires less effort to achieve the necessary results, it does increase the security risk on the machine. It means that a Java application in that codeBase specification will have unrestricted access to the machine resources. When dealing with Unisys supplied components, this should not be a problem.

OpenJDK Installation

The can also be used in Builder to generate Component Enabler files. It can also be used with clients that rely on the COM or Java bridging support, previously provided by Microsoft JVM. For example, VB Clients, Active Server Pages, and so on.

Before installing OpenJDK, you must download the install package. You can download the installer package from <https://learn.microsoft.com/en-us/java/openjdk/download>.

After downloading the installer package, you can install the package by following the instructions in the following link: <https://learn.microsoft.com/en-us/java/openjdk/install>

Installing the Presentation Client

The Presentation Client can be installed independently of the Component Enabler Development environment. Select **Presentation Client** on the main setup window to install the Presentation Client as a standalone client on a user workstation.

Notes:

- *If two instances of the installation wizard appear, close one instance.*
- *The Presentation Client is installed by default with the Component Enabler Development environment. A development workstation does not need to re-install the Presentation Client using this option.*

Requirements

For standalone client mode, you require a network machine with TCP/IP services installed.

Standalone Client

The following operating systems have been tested and are supported for use with the Presentation Client:

- Windows 10 Enterprise (x64) November 2019 v1909
- Windows 10 Professional (x64) v1909
- Windows Server 2019 (LTSC) Standard, Datacenter

You must install one of the following in the client workstation:

- Oracle Java SE 11 or later
- OpenJDK 11 or later

Setup

Depending on the mode of operation, your environment can be set up in different ways and installation files might be allocated to different locations.

The installation files are described in the following tables:


Standalone client specific

File	Description
LincViewer.jar	Contains the class files that are required to run the Presentation Client as an application.


Common files

File	Description
Configuration file	Contains the configuration parameters for connecting to host applications.
ViewerResources.properties	Contains localization and internationalization strings.
Class files	The generated class files for the Enterprise Application Environment application.
Images and Lists	Any images or list box data files required by the graphical screens.
ViewerHelp.jar	Contains the online help for the Presentation Client.
XmlParserAPIs.jar XercesImpl.jar	Support library for reading XML formatted configuration files.

You can also run the AB Ready tool to check the status of the prerequisite software for Presentation Client installation.



104072



104073

Standalone Installation for Windows Operating Systems

Selecting this installation option installs only those files required to run the Presentation Client as a standalone application on a Windows workstation.

1. On the main Client Environment installation screen, select **Presentation Client**.
The InstallShield Wizard appears.
2. On the InstallShield Wizard, click **Next**.
3. After you read and accept the terms in the license agreement, select **I accept the terms in the license agreement** option, and then click **Next**.
4. Specify the installation directory. The default directory is displayed, but you can select another location.
5. Click **Next**.
6. In the **Java Folder** screen that appears, you can either set the Java path to the default Java folder or click **Change** to set a different location.

You require a Java version 11 or later of Oracle Java SE or OpenJDK. If the required Java version is unavailable, an error message appears.

Note: You must download the OpenJDK files and extract them in the 64-bit folder (Program Files\OpenJDK).

7. A default configuration file, config.xml, is copied to the installation directory. The default configuration file initially has no entries, as configuration information is site-specific. However, the administrator can update the file using the Configuration Assistant (or manually using a text editor).

The updated file can be included as part of a customized version of the Presentation Client installation image. When the customized Presentation Client installation package is exercised, the updated configuration file is copied to the Presentation Client installation directory. Refer to [Customizing the Presentation Client Installation](#) for more information.

A shortcut is added to the Start screen, All apps, Agile Business Suite 8.0, Presentation Client. The shortcut references the default configuration file, config.xml.

Standalone Installation for non-Windows Operating Systems

The installation of the Presentation Client on non-Windows platforms is a manual process:

1. Set up the Presentation Client directory on the workstation; for example, C:\NGEN_CE\Presentation Client.
2. Copy the Presentation Client jar files to the directory. Ensure the following files are copied:
 - ViewerHelp.jar
 - LINCViewer.jar
 - xmlParserAPIs.jar
 - xercesImpl.jar

3. Set up a directory which class files can either be copied to, or downloaded from a remote location; for example, C:\CE\classes.
4. Copy the configuration file to the Presentation Client directory, or another accessible location. Refer to Using the Configuration Assistant in the *Agile Business Suite Component Enabler Guide* for more information on creating a configuration file.
5. Ensure the following files and directories are included in the classpath:
 - Viewer.jar file.
 - Location of the generated form class files. If these files are not located within the Presentation Client directory, the download destination option must be specified in the configuration file.
6. Ensure the Oracle JDK 11 or OpenJDK 11 and their later version is installed on the workstation.

To start the Presentation Client, run the Java interpreter from the command line using the following syntax:

```
javaw com.unisys.jellybeans.views.LINCViewer <command line options>
```

The following example starts the Presentation Client as an application accessing the system sample, as defined in the configuration file *config.xml*.

```
javaw com.unisys.jellybeans.views.LINCViewer -config=config.xml -system=sample
```

If applicable, you can create a desktop icon or menu item to initiate the Presentation Client.

Uninstalling the Presentation Client

Uninstalling the Presentation Client on non-Windows platforms is a manual process. It is a matter of reversing the installation instructions and deleting the relevant files.

Using the Redirector

If an applet needs to make a socket connection to a socket other than the one from which it was originally loaded, the connection to the Remote Access server has to pass through a redirector program on the Web server. This occurs if the system and the Web server supplying the client components are running on different systems.

A redirector program for the Windows 11 environment is supplied with AB Suite 8.0, as CE\ReDIR\tcpredir.exe.

There are two commands to use with the redirector:

- **tcpredir -install**

installs the redirector.

```
tcpredir -install  
  <1st lport#>:<1st machine name>:<1st rport#>  
  <2nd lport#>:<2nd machine name>:<2nd rport#>
```

where:

- “lport#” is the port number to listen on
- “machine name” is the name of the machine to redirect to
- “rport#” is the port number to redirect to

This allows the Web server to connect to multiple systems. After installing the redirector, you must start it before can be used.

To start the redirector, go to **Control Panel, Services** on your Web server. Select **TCP Redirector**, and then click **Start**. To stop the redirector, go to **Control Panel, Services**, select **TCP Redirector**, then click **Stop**.

- **tcpredir -remove**
removes the redirector.

Using Component Enabler with Browsers

Component Enabler has been qualified with the Microsoft Internet Explorer Web browser. You can download Microsoft Internet Explorer from:

<http://www.microsoft.com/ie/>

Using Component Enabler with COM Based Applications

In order to access COM based applications using Component Enabler, you have a couple of options: (1) Use the Oracle Java Plugin with the ActiveX Bridge support for the Java/COM interface. (2) Use the CEWindowsAPIJavaStyle interface in the .NET based Component Enabler Runtime. Refer to the *Agile Business Suite Component Enabler User Guide* for more information about interfacing to COM based applications.

Customizing the Presentation Client Installation

The Presentation Client installation software includes several configuration options that allow you to prepare a customized version of the installation package. The administrator can make a copy of the Presentation Client installation directory from the Client Environment folder, present within the CD Developer folder, and then make modifications in certain areas to develop a Presentation Client runtime installation package that meets site-specific requirements. The areas that can be customized are described below.

Default Configuration File

A skeleton configuration file called config.xml is provided in the installation directory for the Presentation Client. This configuration file can be overwritten by the administrator with a site-specific configuration file prepared with the Configuration Assistant. A copy of the Presentation Client installation directory can include the new configuration file. This can then be used for installation on user workstations at the customer site.

Icons

If the configuration file refers to specific icons that the Presentation Client requires at runtime, these icons can be copied to the...\Icons directory of the installation package. The contents of the icons directory is copied to the installation directory of the user's workstation.

Application Classes

The generated application classes for an Enterprise Application Environment system can also be bundled with the Presentation Client installation. Copy the classes to the...\Classes directory of the installation package.

During installation, the directories and files within the Classes directory of the installation package is copied to a Classes directory beneath the installation directory on the user's workstation.

The Java class files must be assembled within the required Java package structure, and this is maintained during installation.

For example, if you have generated a system called "sample" with a package prefix of "com.unisys" and a bundle name of "all", the structure beneath the ...\Classes directory should contain the following directories and associated contents:

```
Com\unisys\sample\all\ispecs (Data classes)
Com\unisys\sample\all\views\lang1 (Presentation classes)
```

This level of customization allows workstations to be initially set up with all the required runtime components to achieve a connection with the Enterprise Application Environment system using the Presentation Client. Subsequent updates can then be downloaded as necessary from a Web server.

This type of installation customization is suited to users that want to use software distribution mechanisms to deploy the Presentation Client and associated runtime components, to many user workstations. In conjunction with the silent mode operation (refer to [Presentation Client Silent Installation](#)), this offers a convenient mechanism for installing the Presentation Client software, and also configuring it with the required site-specific components and configuration options.

Presentation Client Silent Installation

Automated electronic software distribution (silent install) enables the installation of Presentation Client as a stand-alone application across a number of Windows operating system workstations, thus reducing administration time and ensuring consistent environments. Silent installation can be used in conjunction with System Management Services to automatically install Presentation Client from network servers on a large number of workstations.

Requirements

Before running the silent installation, ensure the JRE is installed on the target workstations, as it is not included with the silent installation. You can perform a silent installation of the Java Runtime Environment by performing the instructions in https://docs.oracle.com/javase/8/docs/technotes/guides/install/windows_installer_options.html.

Performing a Silent Installation

A response file is required in order to run a silent installation. The response file can either be created automatically or manually. The following procedure for performing a silent install includes the automatic creation of the response file.

Step 1: Automatically creating a response file

1. From the command prompt change the location to the directory containing the Setup.exe file.
2. Run the installation including the additional flags.

```
-a -r /f1<path><filename.iss>
```

where:

Flag	Description
-a	Signals that additional parameters are to be passed to the executable file.
-r	Sets the installation in record mode.
-f1	Specifies the location and name of the response file to be created, where <i><path></i> is the location and <i><filename.iss></i> is the file name. If this switch is omitted, the default file setup.iss is created in the Windows directory.

For example,

```
Setup.exe -a -r /f1C:\CEInstall\CEsetup.iss
```

Note: *There is no space between /f1 and <path>.*

3. Proceed through the installation process and select the options you want to use in the silent installation.

When the installation is complete the response file is created in the specified directory and contains information similar to the following example:

```
[InstallShield Silent]
Version=v6.00.000
File=Response File
[File Transfer]
OverwrittenReadOnly=NoToAll
[{2EFFFFB81-3AAF-493B-B3A9-E52542AA555F}-DlgOrder]
Dlg0={2EFFFFB81-3AAF-493B-B3A9-E52542AA555F}-SdWelcome-0
Count=7
Dlg1={2EFFFFB81-3AAF-493B-B3A9-E52542AA555F}-SdLicense-0
```

```
Dlg2={2EFFFFB81-3AAF-493B-B3A9-E52542AA555F}-AskText-0
Dlg3={2EFFFFB81-3AAF-493B-B3A9-E52542AA555F}-SdAskDestPath-0
Dlg4={2EFFFFB81-3AAF-493B-B3A9-E52542AA555F}-SdSelectFolder-0
Dlg5={2EFFFFB81-3AAF-493B-B3A9-E52542AA555F}-SdStartCopy-0
Dlg6={2EFFFFB81-3AAF-493B-B3A9-E52542AA555F}-SdFinish-0
[{2EFFFFB81-3AAF-493B-B3A9-E52542AA555F}-SdWelcome-0]
Result=1
[{2EFFFFB81-3AAF-493B-B3A9-E52542AA555F}-SdLicense-0]
Result=1
[{2EFFFFB81-3AAF-493B-B3A9-E52542AA555F}-AskText-0]
szText=11779900
Result=1
[{2EFFFFB81-3AAF-493B-B3A9-E52542AA555F}-SdAskDestPath-0]
szDir=C:\Alinc
Result=1
[{2EFFFFB81-3AAF-493B-B3A9-E52542AA555F}-SdSelectFolder-0]
szFolder=Enterprise Application Component Enabler
Result=1
[{2EFFFFB81-3AAF-493B-B3A9-E52542AA555F}-SdStartCopy-0]
Result=1
[{2EFFFFB81-3AAF-493B-B3A9-E52542AA555F}-SdFinish-0]
Result=1
bOpt1=1
bOpt2=0
```

Step 2: Running the silent install

No messages are displayed when running a silent installation. You can create a log file in which all the installation information is recorded.

1. Uninstall any previously installed versions of Presentation Client.
2. To run the installation in silent mode you must first record your actions, and secondly you must run in the silent mode using the recorded script file.

To record:

```
-r /f1<path><filename.iss>
```

For example,

```
Setup.exe -r /f1"C:\setup.iss"
```

To run in silent mode:

```
Setup.exe -s /f1"C:\setup.iss"
```

Flag	Description
-s	Sets the installation into silent mode.
f1	Specifies the location and name of the response file, where <i><path></i> is the location and <i><filename.iss></i> is the file name.
-r	To record the installation to the script file so the silent installation can use it.

Step 3: Checking the log file for errors

To verify the success of the silent install, check the ResultCode value in the [ResponseResult] section of the log file. This value should be zero.

One of the following values is returned as the ResultCode:

Value	Description
0	Successful installation
-1	General error
-2	Invalid mode
-3	Required data not found
-4	Insufficient memory available
-5	File does not exist
-6	Cannot write to response file
-7	Cannot write to log file
-8	Invalid path to the InstallShield Silent response file
-9	Not a valid list type (string or number)
-10	Data type invalid
-11	Unknown error during setup
-12	Dialog boxes are out of order
-51	Cannot create the specified folder
-52	Cannot access the specified file or folder
-53	Invalid option selected

Manually Creating a Response File

Rather than using the automatic process described in the preceding procedure, you can create a response file manually.

The response file has an .iss extension and is similar to an .ini file. The sections of an InstallShield response file must be in the following order:

1. Silent Header

All response files begin with a silent header. The silent header enables InstallShield to identify the file as a valid response file.

The silent header section must contain the following parameters and values:

```
[InstallShield Silent]
Version=v6.00.000
File=Response File
```

Version indicates the version of InstallShield, it is not necessary to specify the specific release level. Use v6.00.000 in all response files. Future versions of Installshield is able to read this version of the response file.

2. Application Header

This is the second section in the response file. It allows developers of the installation setup to identify the setup for which the response file was created, as this is often difficult to determine by looking at the other response file data. It is not used by the setup script or the Setup.exe file.

The application header section contains the following parameters and values:

```
[Application]
Name=<ProductKey from InstallationInfo>
Version=<VersionKey from InstallationInfo>
Company=<CompanyKey from InstallationInfo>
```

These values are derived from the values written to the registry in the call to the Installation Info function in your setup script.

3. Dialog Sequence

This is the third section in the response file. It lists all the dialog boxes needed during the installation, in the order in which they appear. This section is given the heading:

```
[<Product_GUID>-DlgOrder]
```

The dialog box parameters are formatted as follows:

```
Dlg<#>=<PRODUCT_GUID>=<DialogIdentifier>-Dlg-<#>
```

The dialog box numbering sequence begins at zero, meaning the first parameter entry is Dlg0. Each subsequent dialog box number increments by one.

The section is ended with the Count parameter, the value of which equals the number of dialog boxes listed. Because the dialog box sequence begins with zero, the Count value is always one greater than the highest dialog box number.

For example,

```
[{23EAFCCA-361D-11D3-8B0F-00105A9846E9}-DlgOrder]
Dlg0={23EAFCCA-361D-11D3-8B0F-00105A9846E9}-Welcome-0
Dlg1={23EAFCCA-361D-11D3-8B0F-00105A9846E9}-AskOptions-1
Count=2
```

4. Dialog Box Data

The values entered in each dialog box are captured in the response file. Each dialog box listed in the dialog sequence section has its own section.

```
[<PRODUCT_GUID>-<DialogIdentifier>] Result=<value>
Keyname1=<value>
Keyname2=<value>
```

- **[<PRODUCT_GUID>-<DialogIdentifier>]**

identifies the specific dialog box, where <DialogIdentifier> is the value entered for the dialog box in the dialog sequence section.

- Data entered in a dialog box is recorded in the form **Keyname=<value>**. All

dialog boxes return the keyname **Result**, which indicates the button pressed to exit the dialog box. The standard values for **Result** are 12 for the Back button, and 1 for Next or OK.

The keynames for the InstallShield dialog boxes are listed in the following table:

Dialog Box	Keynames	Description
SdWelcome-<#>	Result	1 = Next
SdLicense-<#>	Result	1 = Yes is selected
AskText-<#>	szText	The text from the edit field
	Result	1 = Next
SdAskDestPath-<#>	szDir	The path specified in the edit field
	Result	1 = Next
SdSelectFolder-<#>	szFolder	The folder specified in the edit field
	Result	1 = Next
SdStartCopy-<#>	Result	1 = Next
SdFinish-<#>	bOpt	1 = "Yes, I want to view the README file" is selected
		0 = "Yes, I want to view the README file" is not selected
	bOpt2	bOpt2 is always 0

Installing Business Integrator

Select **Business Integrator** during the Client Environment installation to start the Business Integrator installation. The Installation wizard appears.

Note: If two instances of the installation wizard appear, close one instance.

Refer to the *Agile Business Suite Getting Started with Business Integrator Guide (38265898)* in the Documentation folder, present within the CD Developer folder.

External Components

To run the Business Integrator External Components environment, the following software is required:

- Microsoft Management Console (MMC) 1.2 or later
- Microsoft XML Parser (MSXML) 4.0 and 6.0
- Microsoft Visual C++ 2010 Redistributable Package(x86) might need to be installed manually. Refer to the *Agile Business Suite Business Integrator Getting Started Guide* for more information.

Installing Client Framework

You can install the Client Framework standalone software from the installer as a standalone component on the end-user workstation.

The Client Framework standalone component includes a complete WPF Container application that hosts the Views assembly and displays a view that corresponds to a particular ispec. It also includes the AB Suite Client Framework MVC Scaffolder and the NuGet Packet Manager for Visual Studio 2019.

To install the Client Framework standalone software, perform the following:

1. Click **Client Framework (32-bit)** or **Client Framework (64-bit)** on the Client Environment interface. The Installation wizard appears and a number of checks are carried out on the system to ensure it has the correct underlying system software to complete a satisfactory installation.

Notes:

- *If two instances of the installation wizard appear, close one instance.*
 - *If the Client Framework software is already installed on your machine as a separate instance, the Program Maintenance dialog box appears; you can choose to repair or remove the Client Framework software.*
2. If the checks are successful, a welcome dialog box appears, followed by a license dialog box. To accept the conditions and continue with the installation, click **I accept the terms in the license agreement**; if not, click **I do not accept the terms in the license agreement**.

Accepting the license agreement allows you to select the target drive and directory for the installation, if you do not want to accept the default installation location.

3. Click **Next** to proceed with the installation.

You can click **Back** to make changes, if any.

At the completion of the installation, the Installation Shield Wizard Completed dialog box appears. This screen allows you to view the readme file and the Windows Installer log file. If you want to view the readme file or the Windows Installer log file, select the respective check box.

4. Click **Finish** to complete the installation.

Configuring WPF Client Container

Before running applications, you must edit the "<Client Technology Folder Name>_Config.rtxml" configuration file. For example, if the Client technology folder in System Modeler has the name "WPFClient", the configuration file should be "WPFClient_Config.rtxml". This file contains configuration information to enable the WPF client to find and connect to the application component. This file is automatically created during the generation of the system. The administrator might have already modified this configuration file in the installation package. Check with your administrator before proceeding to modify the file.

A default copy of the configuration file is located at <System Modeler project folder>\Access Layer API Deploy.

The following entries of the configuration file might need to be edited:

- <system name> should be set to a string with the name of the system. This name appears on the title bar of the WPF client application window; for example, <system name = "Sample">
- <startupSystem name> should be set to the same string as <system name>. Note that you can have multiple <system name> sections in the configuration file. This <startupSystem name> entry specifies which system is started when you first open the WPF Client; for example, <startupSystem name="Sample">
- <componentName> should be set to the name of the COM Program ID that the system was generated with for example, <componentName>SAMPLE</componentName>. Contact your administrator for this value. This name is case-sensitive and must correspond to the case of the actual name of the COM Prog ID.
- <runtimeServer> must contain the machine name where the runtime system was deployed and installed. Contact your administrator for this value. Use "localhost" if you generated a test system to your own machine.
- <downloadServerURI> is a location where the required WPF Client assemblies are retrieved from. This can be a file share on the local or remote machine; for example, <downloadServerURI>file://C:\Users\<User Name>\Documents\Visual Studio 2019\Projects\ForwardModel\Access Layer API Deploy. It can also be an FTP or HTTP site from where you can download the assemblies.

To run the WPF Client Container, setup a shortcut that allows you to specify the name and location of the Configuration file as a parameter; for example, "<WPFClient Installation Path>\WpfClient.exe" "C:\Users\<UserName>\Documents\Visual Studio 2019\Projects\<Technology Folder>\Access Layer API Deploy\WpfClient_Config.rtxml".

Installing Windows TLS Certificate

For Windows clients, while using Secure RATL, OS2200 Secure FTP, MCP Secure FTP, or MCP Secure Appl Bld the appropriate TLS certificates must be installed in the Microsoft Management Console (MMC) in the host where application bundle is available. The chain of certificates required for the TLS connection must be installed in the client machine.

Perform the following steps to install the certificate:

1. Click **Start**, point to **All apps**, expand **Windows System**, and then click **Run**. Enter certlm.msc in the **Run** window. Alternatively, enter certlm.msc in the search box, and then press the **Enter** key.
2. To import the certificate into Trusted Root Certificate Authorities in Certificates, expand **Trusted Root Certificate Authorities** and select **Certificates**.
3. Right-click **Certificates**, point to **All Tasks**, and then click **Import**.
4. Click **Next** in the **Certificate Import Wizard**.

5. Browse to the path where the certificate that you want to install is located, and then click **Next**.
6. Click **Finish**.

A pop up is displayed to indicate that the import is successful.

Certificates are installed successfully and can be viewed under the **Trusted Root Certificate Authorities** in **Certificates**.

Notes:

- Earlier levels of TLS and SSL are not supported due to known vulnerabilities. Only TLS 1.2 level is supported. It is recommended to enable only TLS 1.2 on Windows when using an encrypted Remote Access Server connection to access an AB Suite application.
- When configuring the client for Secure RATL, the HostURI should be entered in the format "x-<protocol>:<hostname>:<port>", where, the protocol is ratlts instead of ratl, the hostname is the name of the server machine where runtime application is running and the port number is the port on which RATL service is running in server machine.

For example,

```
"<add key="HostURI" value="x-ratlts:localhost:2449"/>"
```

- Refer to *How To Secure Communication Between the Client and the OS 2200 Host* in the *Documentation Libraries* page on the *Product Support Site* for more information.

Change, Repair, or Uninstall Agile Business Suite Client Environment

You can modify, repair or remove the Client Environment installation components by using the Windows Programs and Features application available from the Control Panel window.

Note: The Component Enabler installation only provides for the removal of the application. Modify or Repair are not available options.

To perform any of these functions, perform the following:

1. Point to and click the **Start** icon in the bottom-left corner of the screen.
2. Right-click a blank part of the **Start** screen and then select **All apps**. Select **Control Panel** from the **Apps** screen to display the Control Panel window.
3. Select **Programs and Features** to display the Programs and Features dialog box listing all the installed programs.
4. Locate the program that you want to remove, from the list and click **Change/Remove** to display the Setup Maintenance dialog box.
5. Click the **Change/Repair/Uninstall** option for the operation that you wish to undertake.
6. Click **Next** to continue with the selected operation.

The available maintenance operations are shown below.

Change

Change allows you to add Client Environment components that were not installed during the original installation, or remove selected components via the Feature Selection Screen.

If you select the Change operation, when you click **Next** and no hotpatch exists, the Feature Selection dialog box is displayed. From the list of components select the ones that you wish to add, or deselect the ones that you wish to remove.

If a Hotpatch is already installed, then a message box is displayed to request that you manually uninstall the Hotpatch prior to continuing with the modification. Click **Confirmation** to terminate the maintenance. You must then uninstall the hotpatch before recommencing with the modification. After the modification is complete, you should re-install the Hotpatch.

Repair

Repair the Client Environment installation by reinstalling all non-customizable files in the same location as the previous installation. If any of the files were accidentally deleted or modified, then this option restores the software back to its original state.

If you select the Repair operation, when you click **Next**, and no hotpatch exists, the installation proceeds automatically.

If a Hotpatch is already installed, then a message box is displayed to request that you manually uninstall the Hotpatch prior to continuing with the modification. Click **Confirmation** to terminate the maintenance. You must then uninstall the hotpatch before recommencing with the modification. After the modification is complete, you should re-install the Hotpatch.

Uninstall

Remove all non-customizable Client Environment files and remove all the registry entries. This restores the computer to the state prior to installation of the Client Environment. If a Hotpatch is already installed, the setup program automatically uninstalls the Hotpatch before uninstalling the Client Environment.

If you select the Uninstall operation, when you click **Next**, a message box is displayed requesting you to confirm or cancel the operation. If you confirm the operation, the Client Environment is uninstalled.

Section 6

Runtime for Windows[®] Operating System Installation

This section describes how to install Agile Business Suite Runtime for the Windows Operating System.

Required System Software Configuration


The system software configuration required to support Agile Business Suite Runtime for Windows is detailed in the table below.

Required Item	Comments
- Windows Server 2019 Standard, Datacenter (LTSC) - Windows Server 2019 Datacenter Edition (LTSC) - Windows Server 2022 Datacenter Edition (latest update)	Windows 10 is not supported on the AB Suite Windows Runtime production environment, but can be used for testing purposes. You require latest updates for testing. Other Windows Operating System editions, such as Home or Server Core Editions are not supported and might not work with AB Suite 8.0 Runtime for Windows. AB Suite 8.0 currently supports 64-bit Windows 10 (1909 version) , Windows Server 2016 (LTSC versions), and Windows Server 2019 (LTSC versions) only. It does not support 32-bit Windows. Windows Server Semi-Annual Channel versions, such as version 1803, and 1809 are not currently supported.
Qualified for .NET Framework 4.8	This is a requirement for all features. .NET Framework 4.8 is required for AB Suite Runtime for Windows.
Internet Information Services	The version of IIS depends on the operating system that you are using. Refer to your Microsoft information for the appropriate version. This requirement is only needed for certain features.
Message Queuing	This requirement is only needed for certain features.
- SQL Server Enterprise Edition 2019 or - SQL Server Standard Edition 2019	AB Suite 8.0 Runtime for Windows currently supports Enterprise and Standard Edition of SQL Server 2019 only. You require the latest updates for testing.


Runtime for Windows® Operating System Installation

Required Item	Comments
Microsoft Visual C++ Redistributable for Visual Studio 2019	This requirement is a must for installing Agile Business Suite 8.0 for Windows Runtime on a Windows server. You can install the runtime without Developer or Visual Studio 2019. However, the Runtime is dependent on Visual Studio 2019 runtime libraries, which are freely available. You can download these libraries from: https://support.microsoft.com/en-in/help/2977003/the-latest-supported-visual-c-downloads Note: x86 redistributables are still required on an x64 bit machine. You should install these Visual Studio 2019 runtime components before installing the GCA. Visual C++ for Visual Studio 2019 is also required as some parts of AB Suite 8.0 Runtime for Windows are built using Visual C++.
Microsoft OLE DB Driver for SQL Server	This is a requirement for all the Runtime features. AB Suite uses the TLS 1.2 features that come with the new Microsoft OLE DB Driver for the SQL Server to provide better security during Windows Runtime and Debugger sessions.

You can also run the AB Ready tool to check the status of the prerequisite software for Windows Runtime installation.



104074



104075

Minimum Hardware Requirements

This section describes the minimum recommended hardware requirements for running Runtime for Windows.

Hardware	Runtime
Processor	4 core, 2 GHz
Memory	8 GB RAM
Disk space	250 GB
Monitor	LCD

Note: Check with your vendor for the dependent software disk space needed. Your disk space allocation on the Windows operating systems server for Runtime should be based on the following approximate allocation of disk space:

- 245 to 250 MB Agile Business Suite Developer software
- 25 to 30 MB Agile Business Suite Runtime software
- 20 to 50 GB Visual Studio 2019 software minimum installation
- 6 GB SQL Server 2019 software minimum installation
- Actual disk space requirements for SQL Server database files depends on database use. (Remember to allow space for the databases to grow, if needed.)

Installing Runtime for Windows

Agile Business Suite Runtime for Windows can be installed on any workstation or as a network installation with shared components. All installation types are detailed in this document. When you are installing Runtime for Windows, it appears as the following software modules:

Module	Description
Runtime	Installs runtime core, deploy server and shared components. Requires .NET Framework 4.8.
AdminTool	Installs the client administration tool as a Microsoft Management Console “snap in”.
DB Migrate Utilities	Installs only database migration tool components. The AB Suite Runtime infrastructure is not installed with the DB Migrate Utilities. It requires Microsoft SQL Server 2017/2019 Integration Service package.

Notes:

- You can install AB Suite 8.0 Runtime with the earlier versions of AB Suite Runtime, such as AB Suite Runtime 7.0, 6.1, 5.0, 4.0, 3.0, and 2.0
- You can install AB Suite 8.0 Runtime with AB Suite 8.0 Developer only.

COM+ Network Access in Windows 11 and Windows Server 2019 / 2022

In the Windows 11 and Windows Server 2019 / 2022 operating systems COM+ network access is enabled in the windows registry by enabling a registry key and not through the Add Roles and Features wizard of the Server Manager window.

Caution


The registry key must be enabled by experienced administrators only.

To enable a registry key in the windows registry

1. Open the Registry Editor window by performing either of the following:
 - a. In the search box on the task bar, enter regedit and select **regedit** from the list.
 - b. Right-click **Start** and then select **Run**. In the Run window, enter regedit and click **OK**.
2. In the **User Account Control** dialog box, click **Yes**.

The Registry Editor window appears.

3. Navigate to Computer\HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\COM3.



009050

4. Double-click RemoteAccessEnabled.

The **Edit DWORD (32-bit) Value** dialog box appears.

5. In the **Value data** text box, enter 1.
6. Click **OK**.

Setting up User Accounts

Prior to installing Runtime, you must set up and configure user accounts for “Application User” and “Application Administrative User”. The installation will ask for the name, domain, and password of these accounts. The installation checks that the accounts exist and verify the credentials supplied. These credentials are then used to initially configure the identities of those components that are required to run as the Application User, or the Application Administrative User.

Refer to [Configuring User Accounts](#) for more information about the configuration details that might need to be applied for these user accounts after installation.

Unisys Installation Interface

When you double-click the RuntimeCDBrowser.exe and click **Runtime Environment**, the Unisys Installation Interface appears. The Unisys Installation Interface controls the installation process and indicates the product name. When this interface appears, the installation program checks if you have administrative rights on the machine, and if your machine has the required operating system. If any of these checks fail, a message box appears and you are prompted to terminate the installation.

If the checks are successful, a welcome dialog box is displayed, click **Next**. It is followed by a license dialog box. Click **Accept** on the license dialog box, if you want to continue with the installation.

You are then given the opportunity to select the type of installation that you wish to initiate, and to select the target drive and directory for the installation if you do not wish to accept the default installation location.

The options are:

- **Complete**

Select this option to install all components of Runtime.

- **Custom**

Select this option to display the Select Features dialog box to allow you to select the components that you wish to install.

Click **Next**. The installer displays the message to select a certificate for RATL TLS. You can select one of the following options:

- Click **Yes** to select a certificate during installation, and then select the certificate from the list of valid certificates.
- Click **No** to manually install the certificate using the Administration tool before performing any transaction using RATL.

Notes:

- *AB Suite 8.0 uses secure RATL for Windows by default. However, if you want to use unsecure RATL, you can modify it manually.*
- *Ensure that a valid certificate is installed from a trusted CA before installing the Runtime.*
- *Earlier levels of TLS and SSL are not supported due to known vulnerabilities. Only TLS 1.2 level is supported. It is recommended that only TLS 1.2 is enabled on Windows Runtime when using an encrypted Remote Access Server connection to access an AB Suite Windows Runtime application.*

Click **OK**.

Custom

When you select the **Custom** option from the Installation Interface, the Select Features dialog box is displayed which provides the following options:

- Runtime
- AdminTool
- DB Migrate Utilities — The DB Migrate utilities and their functionality are discontinued as EAE is no longer supported.

Runtime

Select this option to install the Runtime software, which includes runtime core, deploy server and shared components.

When you install core runtime, protocol adapters are automatically installed. The following protocol adapters are installed:

- RATL over TCP/IP – this is a legacy protocol that is used by version 3.x of Component Enabler.
- RATLTLS over TCP/IP – this is a secure RATL protocol that is used to exchange secure data between the client and the server.
- RATL over MSMQ – for Component Enabler to use Remote Access Server (RATL) over MSMQ.
- SOAP over HTTP (Web Services) – SOAP over a HTTP connection is the current standard.
- SOAP over MSMQ – uses the SOAP adapter to call over MSMQ.
- HUB - a proprietary protocol that allows other Agile Business Suite systems to talk to each other.
- NOF/OFF/USER/GLI – proprietary protocols that are mainly used to migrate applications from mainframe hosts to Windows hosts.

AdminTool

Select this option to install the client administration tool as a Microsoft Management Console “snap in”.

Completing the Installation

After you select the components that you want to install, click **Next** to display the Start Copying Files Screen. This allows you to review the installation settings before completing the installation. This screen displays the components that are selected and the installation directory. If you are satisfied with the settings, click **Next** to proceed with the installation, otherwise click **Back** to make changes.

The installation then checks to see if the required level of Microsoft Visual Studio .NET Framework exists on the machine, then the installation proceeds, otherwise a warning message is given and you are asked to terminate the installation.

At the completion of the installation, the Installation Complete Screen appears. This screen displays the following options:

- **Update Runtime in PATH environment variable** – adds the AB Suite Runtime installation path to the system PATH variable when you select this check box and click **Finish**. You can clear the check box if you do not want to add the AB Suite Runtime installation path to the system PATH variable.

Note: *The benefit of adding the AB Suite Runtime folder to the PATH is that utilities such as the RUNREP executable will be more easily found and can be executed without full path qualification. If you have multiple versions of AB Suite Runtime installed side-by-side then you should not add the runtime folder to the PATH environment variable as this might result in the wrong executable files being accessed at runtime.*

This check box is selected by default.

- **Show the readme file** – displays the readme file when you select the check box and click **Finish**. You can clear the check box if you do not want to view the readme file. This check box is not selected by default.
- **Show the Windows Installer log** – displays the AB Suite <version> Runtime.log file when you select the check box and click **Finish**. You can clear the check box if you do not want to view the log file. This check box is not selected by default.

Click **Finish** to complete the installation.

Silent Installation

The Windows Runtime Installation Package has the extension .msi and the Silent Installation can be run using the msixec.exe utility. When the command line argument "/qn" is passed to the utility, it installs the Windows Runtime Installation Package without Graphical User Interface (GUI) that is, no dialog boxes, no user prompts requesting information (Install directory). The progress of the installation whether the installation has completed successfully or failed is written to a log file. The log file includes the status, warning and error messages.

Implementation of Silent Installation

From the command prompt, executing the following command line arguments ":> msixec.exe /i "<path of the AB Suite 8.0 Runtime.msi>AB Suite 8.0 Runtime.msi" /qn <parameters> installs the Windows Runtime Installation package in silent mode.

The purpose of the Silent Installation is to automate the installation without Graphical User Interface (GUI) of Windows Runtime Installation. This means, no dialog boxes, no user prompts requesting information is displayed to the user.

Processing

The command and parameters to execute the AB Suite packages are as follows:

Commands/Parameters	Values
msixec /i	Example: <default directory>\AB Suite 8.0 Developer\Product Configuration 1\Release 1\DiskImages\Disk1\AB Suite 8.0 Developer.msi
/qn INSTALLDIR =	Example: C:\Program Files\Unisys\AB Suite 8.0\
AgreeToLicense	Yes
ADDLOCAL	ALL
APP_USER_DOMAIN=	.
APP_USER_NAME=	Example: AppUser
APP_USER_PASSWORD=	Example: App1User
APP_ADMIN_DOMAIN=	.

Commands/Parameters	Values
APP_ADMIN_NAME=	Example: AppAdminUser
APP_ADMIN_PASSWORD=	Example: App1AdminUser
PASSDATA=	Example: C:\AB Suite 8.0\Data\
PASSBUILDERCACHE=	Example: C:\Program Files\Unisys\AB Suite 8.0\Builder Cache\
PASSBUILDEROUTPUT=	Example: C:\Program Files\Unisys\AB Suite 8.0\Builder Output\
/l*v	Example: C:\Temp\AB Suite 8.0.Log

Where,

msiexec is the executable program of the Windows Installer to interpret installation package and install products on the target location.

/i switch is used to install the package from the command line.

INSTALLDIR is a property for specifying the location where the Windows Runtime Installation Package is installed.

/qn switch is used to suppress the dialog boxes displayed for input and output to the user.

/l*v switch is used to create a log file.

For example, to install Runtime through Silent Installation, run the following command from the command prompt:

```
msiexec /i "Agile Business Suite 8.0 Runtime (64 bit).msi" /qn /norestart INSTALLDIR="C:\Program Files\Unisys\AB Suite 8.0\" AgreeToLicense=Yes ADDLOCAL=ALL APP_USER_DOMAIN=. APP_USER_NAME=AppUser APP_USER_PASSWORD=App1User APP_ADMIN_DOMAIN=. APP_ADMIN_NAME=AppAdminUser APP_ADMIN_PASSWORD=App1AdminUser PASSDATA="C:\AB Suite 8.0\Data" /l*v c:\temp\Runtime.log
```

Uninstall Agile Business Suite Runtime

You can uninstall the AB Suite Runtime from the Control Panel.

To uninstall the AB Suite Runtime, perform the following

1. Open **Programs and Features** from **Control Panel**.
2. From the list of installed programs, right-click **Agile Business Suite Runtime**, and then select **Uninstall**.
3. Click **Yes** when prompted to confirm and continue with the operation.
Click **No** if you do not want to uninstall the AB Suite Runtime.

Section 7

Runtime for Windows® Operating System Configuration

This section provides details of the configuration required in setting up the Runtime for Windows Operating System environment.

Configuring User Accounts

Runtime requires two users to be created, under whose identities the various operations will run.

The Application User's identity is used for the standard operations and has a lower privilege level. The Application Administrative User's identity is used to perform administrative tasks for which a higher privilege level is required.

Refer to [Preparing for Installation of Agile Business Suite](#) for more information on how to create and configure the user accounts.

These users must be created prior to installation. It is up to the system administrator to decide which accounts are used to represent the Application User and the Application Administrative User.

The User accounts must be granted access to the server as described in [Server Configuration](#).

The Application User

The Application User has a normal Windows operating system user account from either the local or network domain, to which the following rules apply:

- The user account is required to have direct or indirect membership of the local "Users" group, or its equivalent.
- The account name must not contain any blanks.
- The account must not have a blank password.
- The account password must not contain any blanks.

The Application User account must be a domain account, if any of the following conditions are true:

- The application would be accessed by any end-user via a domain user account. The processes running as the Application User needs to verify the membership of users in various COM+ Roles. This cannot be done for domain users unless the Application User is also the domain user.
- The database is on a different machine to the application.
- The RATL/MSMQ protocol is used.
- The SOAP/MSMQ protocol is used.
- A printer that is to be used is on a different machine to the application.
- The protocol adapters are running on a different machine to the application, and the RATL, RATLTL, HUB, RATL/MSMQ, SOAP/MSMQ, or SOAP/HTTP protocol is to be used.

The following processes run under the Application User identity:

- RATL protocol adapter
- RATLTL protocol adapter
- RATL/MSMQ protocol adapter
- SOAP/MSMQ protocol adapter
- SOAP/HTTP protocol adapter
- HUB protocol adapter
- Report Session Manager
- Hub Transaction Context
- Hub Transaction Coordinator
- Print Configuration Manager
- Segment Session Manager
- The processes housing the applications.
- The process housing the generated reports.

Application User Account Required Rights and Privileges

The account should not be granted any privileges beyond those specified below.

On all machines:

- The “Log on as a batch job” required due to some batch processes assuming the Application User’s identity.
- Log on as a service

On the machine hosting the protocol adapters:

- Log on as service is required to be able to log into the gateway services on the machine.

On the machine hosting the databases, when the databases are on a different machine to the applications:

- “Access this computer from the network” required in order to connect to the database remotely.

On Windows 11, Windows Server 2019, and later Operating Systems

With Windows 11, Windows Server 2019, and later Operating Systems, the User has to be explicitly added to COM+ Users Role. Everyone logging in must be in the COM+ Users Role. By default, only the Administrators Group is added, but with Windows 11, Windows Server 2019, and later Operating Systems, it is only the Administrator version of those users, not the Standard User version that are members of the Administrators Group. Therefore, no Standard User accounts are added by default into the Users Role. In earlier versions of Windows, the user was automatically in the Users Role via its membership of the Administrators Group. Non-administrative users still had to be added manually to the Users Role. In Windows 11, Windows Server 2019, and later Operating Systems, this rule still applies, but now everyone is a non-administrative user by default.

The Application Administrative User

The Application Administrative User has a normal Windows Operating System user account from either the local or network domain. It is required to have direct or indirect membership of the local “Administrators” group, or its equivalent.

The Application Administrative User account must be a domain account if any of the following conditions are true:

- The application would be accessed by any end-user via a domain user account. The processes running as the Application Administrative User needs to verify the membership of users in various COM+ Roles. This cannot be done for domain users unless the Application Administrative User is also the domain user.
- The database is on a different machine to the applications.
- The applications are deployed remotely.

If the Application Administrative User account is a domain account, then it must **not** have a roaming profile.

In addition, if applications are to be deployed remotely, the Application Administrator User’s account must be marked as “Account trusted for delegation” in the domains active directory. This applies only to Windows 2010 and later, domains. The change might not be immediately visible as it can take some time to propagate throughout the machines within the domain. This is applicable for all the supported operating systems. Therefore, the deployment server running as the Application Administrative User impersonates the user that invokes the deployment to access the resources on the developer machine. This requires the invoking user to be given the administrator privileges in the runtime server and the Application Administrative User to be given the “Account trusted for delegation” privilege.

Note: In Windows Server 2012 and later version domains, to provide delegation privileges to the Application Administrator User account and mark it as “Account trusted for delegation”, you should assign Service Principal Name (SPN) to the Application Administrator User account in the active directory.

For example, to assign an SPN name ‘https/AppAdminUser’ to AppAdminUser account, run the following setspn command on domain controller:

```
setspn -a https/AppAdminUser AppAdminUser
```

where, the first parameter, https/AppAdminuser, is an SPN name and the second parameter, AppAdminUser, is an account name. You can also prefix a domain name with the account name, for example,

```
setspn -a https/AppAdminUser MyDomain\AppAdminUser
```

The RuntimeServiceImpersonationLevel registry key provides an alternate method of deployment. With this registry key, you can choose to deploy a system with or without the Application Administrative user having delegation privileges. The RuntimeServiceImpersonationLevel is of the type String and is stored in the runtime machine under the following registry key:

```
\HKEY_LOCAL_MACHINE
\SOFTWARE
\Unisys
\AB Suite
\8.0
\SM Runtime
```

where

```
"RuntimeServiceImpersonationLevel"= string:"Anonymous/Delegate"
```

Note: The registry setting must be reapplied after each IC upgrade.

The RuntimeServiceImpersonationLevel registry key can be assigned the following values that represent various impersonation levels:

- Anonymous (Security Anonymous) – When you assign the Anonymous value, the deployment process is initiated by using the Application Administrative User account instead of the user that invokes the deployment process. This avoids the Application Administrative User to be given the “Account trusted for delegation” privilege. Additionally, the user that invokes the deployment does not need to be given the administrator privileges in the runtime server. However, the invoking user must be part of the “Security Administrators” COM+ role under security helper and the “Deployers” COM+ role under deployment server.
- Delegate (Security Delegate) – When you assign the Delegate value, the deployment process is initiated by the user that invokes the deployment process. By default, the impersonation level is set to the Delegate value.

WARNING

Since runtime cannot identify or authenticate the user, who deploys a system, any anonymous user can deploy a system. The anonymous user who invokes the deployment need not be given the administrator privileges in the runtime server. However, the invoking user must be part of the “Security Administrators” COM+ role under security helper and the “Deployers” COM+ role under deployment server. Additionally, the administrators cannot trace the users who have tried to deploy and access the runtime server resources.

By default, the setting is Delegate.

Refer to the *Agile Business Suite Developer User Guide* for more information on deploying with reduced impersonation levels.

Client and server(s) taking part in remote deployment, as well as the client user, and Application Administrative User, must all be part of this domain.

The following processes run under the Application Administrative User identity:

- Database Manager
- Database Reorganization
- Runtime Manager
- System Privileged
- Security Helper
- Deployment Server
- External Call Helper
- Runtime Versioning
- Segment Session Manager

Application Administrative User Account Required Rights and Privileges

The account should not be granted any privileges beyond those specified below.

On all machines:

- “Log on as a batch job” required as some batch processes assumes the Application Administrative User’s identity.

On the machine hosting the applications:

- “Replace a process level token” required to run deployment packages and make external calls.
- “Act as part of the operating system” required to verify all domain user credentials.

This privilege is also needed for deployment operations using the non-console Remote Desktop Connections on both operating systems.

On the machine hosting the databases when the databases are on a different machine to the applications:

- “Access this computer from the network” required to be able to connect to the database remotely.

With Windows 11, Windows Server 2019, and later Operating Systems, it is only the Administrator version of those users, not the Standard User version that are members of the Administrators Group. Therefore, no Standard User accounts are added by default into the Users Role. In earlier versions of Windows, the user was automatically in the Users Role via its membership of the Administrators Group. Non-administrative users still had to be added manually to the Users Role. In Windows 11, Windows Server 2019, and higher Operating Systems, this rule still applies, but now everyone is a non-administrative user by default.

Changing Passwords

There might be occasions when it is necessary to change the passwords for the Application User or Application Administration User accounts. When changing the password manually, it must be changed in the following places:

- The required User account; either Application User or Application Administration User.
- All processes running under the User identities need to have their configurations updated with the new password. Refer to [The Application User](#) and [The Application Administrative User](#), for list of these processes.

In addition, to update the Security Utilities with new user information, perform the following steps:

1. Create a text file with name “SecUtil.js”.
2. Open the file in the edit mode and copy the following text:

```
var AppAdminUser = WScript.Arguments(0);  
var wshshell = WScript.CreateObject("WScript.Shell");  
var pwd = new ActiveXObject("SecUtils.PwPersistence.8.0.1");  
pwd.Password(0, "Security\\Users", "UserInfo") = AppAdminUser;
```

3. Save the file.
4. Open the command prompt as Administrator and run the file “SecUtil.js”.

Changing Accounts

It is recommended that the Application User and Application Administrative User accounts not be changed once they are setup. If an account needs to be changed in any way, whether it is simply renamed or an entirely new account is created, all references to the old account must be manually replaced. References in the following places must be updated:

- All Agile Business Suite processes running with the identity of the changed account, as listed in [The Application User](#) and [The Application Administrative User](#).
- All COM+ roles referring to the changed account.
- If the account is recreated, as opposed to renamed, the data files folder needs to have its permissions reset to allow Full Control to the changed account.
- If the account name is recreated, as opposed to renamed, the SID of User account needs to be stored in flat files for Application User and Application Administrative User. They are created in the Data\Private directory. For example:

```
AB Suite 8.0\Data\Private\Security\Users\Application User
AB Suite 8.0\Data\Private\Security\Users\Application Administrative User
```

The SID of the Application User is stored in the Application User file and the SID of the Application Administrative User is stored in the Application Administrative User file.

SQL Server Specific

- The SQL Server login used by the Application User needs to be reconfigured to allow access to the changed account with the appropriate permissions.
- The SQL Server databases used by Agile Business Suite needs to grant the changed account access as a user of the database, and if the changed account is for the Application Administrative User, include it in the db_owner role.
- The SQL Server users utilized by Agile Business Suite in the databases need to have their passwords changed using the Change Database User Password tool. Refer to [Change Database User Password](#).

Change Database User Password

When the Application User and Application Administrative User accounts are changed or their passwords altered, you need to change the passwords of any affected database users. To Change the Database User Password:

1. Open the Administration Tool.
2. Right-click the system node.
3. From the context menu, click **All Tasks > Change DB Password**. The **System Schema Account Password** dialog box is displayed.
4. Enter the new Account Password.
5. Re-enter the new Account Password in the **Confirm Password** field.

Note: Do not use the following characters when changing database schema password as these characters are not allowed in a SQL connection string:

[] () , ; ? * ! @ =

6. Click **Apply** and **OK** to change the DB Server user password.

Note: If you have multiple runtime server instances accessing the same DB Server, you must coordinate the passwords manually. The **Database Login Password Change Option** is selected by default. This option allows you to automatically update the

password for the DB Server instance, if the user id has sufficient privileges. Otherwise, the DB administrator can manually update the password for the SQL Server instance.

Server Configuration

SQL Server

The SQL Server must be configured as follows:

- Allow both SQL Server and Windows authentication (Mixed Mode).
- Use the Local System account in the Services Accounts screen.
- Select Latin1_General Accent-sensitive for the Collation settings.

The Application User must be granted a SQL Server login to the database server that is to be used by Agile Business Suite. The login is case-sensitive and must be in the same case as specified in the Windows Security Accounts Manager database.

Notes:

- *The imported Model database has to be this collation sequence of LATIN1_General_CI_AS because it is case-sensitive considering LDL is casesensitive as well. If the imported Model has a different collating sequence, AB Suite might function unpredictably. Also, note that this collating sequence does not affect Kanji because it uses Unicode for most strings.*
- *Also note that the System Modeler always creates its repository with the collation sequence it requires regardless of the SQL Server Instance default, which is Latin1_General_CI_AS. Runtime Administrators are free to install SQL Server under any kind of collation sequence database they like and Admin Tool can prepare it for use for Runtime.*
- *Some Servers, which have non English locales might require a different collation sequence. Contact your CSC to determine the best collation sequence for your locale. For example, a Latvian locale requires the Latvian_100_Bin.*

Configuring the Default 'sa' Account

When SQL Server is installed, by default the 'sa' account is created with a blank password. In order to ensure that unauthorized users do not gain access to your server, it is recommended that you assign a password to the 'sa' account. If a password is not assigned and an unauthorized user gains access using the 'sa' account, they will have full control of all databases contained on your server.

Runtime Server Configuration

If you are using EOM printing on a Windows 2019 Server, ensure that the **Untrusted Font Blocking** Group policy is disabled on the printer server. If this policy is enabled on the printer server, printed documents may be completely or partially blank, because the operating system is unable to render untrusted (non-default) fonts.

The following link from Microsoft confirms that it is safe to disable this policy with the latest Windows security:

[Untrusted Font Blocking](#)

User Profile Service Configuration

The default behavior of the User Profile service can lead to problems for the AB Suite Windows Runtime system running on a server. This is due to the user registry setting being prematurely unloaded by the operating system resulting in

- The AB Suite Windows Runtime system becoming unresponsive.
- The Windows Application event log displaying the following error:
 - 0x800703fa : Illegal operation attempted on a registry key that has been marked for deletion
- The AB Suite Windows Runtime System log displaying the following error:
 - ReportSessionManager(13264:21080) [Domain\Appuser]; COM Error -2147467259 occurred in :: class CRunningSystem *__cdecl CConfigurationAgent::ConfigDataForSystem(wchar_t *const)

The solution is to enable the following User Profile setting:

- Do not forcefully unload the user registry at user logoff.

To modify the User Profile setting, perform the following:

Prerequisites:

- From Component Services, shut down all the running AB Suite COM+ processes.
- From Services, stop all the AB Suite services.
- Ensure that there are no processes running under AB Suite Application User or Application Administrative User.

1. Open the Local Group Policy Editor.

You can open the Local Group Policy Editor through Run.

- Start **Run** using Windows+R, type **gpedit.msc**, and click **OK**.

2. In the left pane, expand **Computer Configuration**, expand **Administrative Templates**, expand **System**, and then select **User Profiles**.

The User Profiles appear in the right pane.

3. Under Setting, select **Do not forcefully unload the users registry at user logoff**.

4. Click **policy setting** to edit the User Profile.

The Do not forcefully unload the users registry at user logoff window appears.

5. Select **Enabled** and click **OK**.
6. Restart the Runtime server.

Note: The procedure to configure User Profile service applies to Windows 11 and Windows Server 2019.

User Configuration

Client Users

Users accessing an Agile Business Suite application through a client must be authenticated on the machine(s) containing the protocol adapters and applications.

If the protocol adapters and applications are located on the same machine, then the client user requires only a local account.

If the protocol adapters and applications are located on different machines communicating via a network, then the client user requires a domain account.

Regardless of the location of the protocol adapters and applications, the client user's account must have the "Access this computer from the network" option set on the host machine(s), in order to be able to logon.

In order for the client to access an application, the user must be added to the "Users" role on the COM+ application containing the Agile Business Suite application.

Administrative User

Administrative users are those users who are permitted to access applications for administrative purposes. These users are authorized to perform administrative tasks according to the COM+ roles to which they belong.

Note: With Windows 11 Windows Server 2019, and later Operating Systems, it is only the Administrator version of those users, not the Standard User version that are members of the Administrators Group. Therefore, no Standard User accounts are added by default into the Users Role. In earlier versions of Windows, the user was automatically in the Users Role via its membership of the Administrators Group. Non-administrative users still had to be added manually to the Users Role. In Windows 11 Windows Server 2019, and later Operating Systems, this rule still applies, but now everyone is a non-administrative user by default

The following table outlines the available COM+ roles and the administration commands to which they grant access. Refer to the *Runtime Administration Tool Online Help* for more information on how to use the administration commands.

COM+ Roles	Administration Commands
Accountants	HighAccountMonth
	LowAccountMonth

COM+ Roles	Administration Commands
Application Administrators	DeleteReportRecovery()
	HighAccountMonth
	IsHubEnabled
	GetHubStats()
	GetRecoverableReports()
	GetRunningReports()
	ListIspecs()
	LowAccountMonth
	RecoverReport()
	RunReport()
	SendAMessage()
	SetSessionInfo()
	StopReport()
	StopSystem()
	WakeUpReport()
Application Operators	ListIspecs()
	SetSessionInfo()
	StopSystem()
Hub Administrators	GetHubStats()
	IsHubEnabled
Hub Monitors	GetHubStats()
Message Broadcasters	SendAMessage()
Message Senders	SendAMessage()
	(Unicast only)
Report Administrators	DeleteReportRecovery()
	GetRecoverableReports()
	GetRunningReports()
	RecoverReport()
	RunReport()
	StopReport()
	WakeUpReport()
Report Monitors	GetRecoverableReports()

COM+ Roles	Administration Commands
	GetRunningReports()
Report Operators	GetRunningReports()
	StopReport()
	WakeUpReport()
Report Recoverers	GetRecoverableReports()
	RecoverReports()
Report Recovery Administrators	DeleteReportRecovery()
	GetRecoverableReports()
	RecoverReport()
	WakeUpReport()
Report Recovery Operators	DeleteReportRecovery()
	GetRecoverableReports()
	WakeUpReport()
Report Runners	DeleteReportRecovery() (Own reports only)
	GetRecoverableReports() (Own reports only)
	GetRunningReports() (Own reports only)
	RecoverReport() (Own reports only)
	Run Report()
	Stop Report() (Own reports only)
	WakeUpReports() (Own reports only)

Note: The BUILTIN\Administrators group requires authentication with the domain authority, so if you wish to add this group to any COM+ roles, you must ensure that you have installed AB Suite 8.0 GCA using the domain level credentials for Application Users and Application Administration Users. Installing the product using local user accounts results in incorrect behavior for role based authentication.

Configuring Runtime for Normal users

This subsection discusses about configuring AB Suite Runtime so that normal users without administrative privileges can access the Runtime administration tasks. AB Suite Runtime uses the “AB Suite Runtime Administrators” user group on the local machine to allow non-administrative users to access the Runtime administration tasks. By default, the user group does not have administrative privileges. This user group is automatically created on installing AB Suite Runtime, if it does not exist, and removes the user group upon uninstallation of AB Suite Runtime.

WARNING

Allowing access to administrative functionality for non-administrative users is not recommended, as it allows a non-administrative user to perform actions that are normally restricted for system security. You must be aware that the membership of the AB Suite Runtime Administrators group indirectly allows access to the protected system resources.

To view the “AB Suite Runtime Administrators” user group, perform the following:

1. Open Computer Management, accessible from the Administrative Tools folder in the Control Panel.
2. From the Tree view, expand **System Tools, Local Users and Groups, Groups**.

Adding New Non-administrative User to Access Runtime

To allow a new non-administrative user to access the AB Suite Runtime administration tasks, an administrator should add the new or existing user to the “AB Suite Runtime Administrators” user group by using the Component Services MMC snap-in. This allows members of this group to access the AB Suite Runtime administration tasks. By default, the “AB Suite Runtime Administrators” user group is automatically added to the “Runtime Administrators” COM+ role of the Runtime Manager application and the “Deployer” COM+ role of Deployment Server application.

Securing the Runtime Administration Tasks

If a user is not an administrator of the remote server machine, security configuration is required for performing the Runtime administration tasks. To access

- ConfigureLog.exe and ConfigureAdapter.exe, all users must be made part of the “Runtime Administrators” COM+ role of the Runtime Manager component by using the Administration Tool. This can be achieved by adding new users in the “AB Suite Runtime Administrators” group. You can add all the users in the “AB Suite Runtime Administrators” group by using the Component Services MMC snap-in.
- Deploy.exe, all users must be made part of the “Deployer” COM+ role of the Deployment Server component by using the Administration Tool.

The non-administrative users in the “Deployer” COM+ role cannot perform deployment operations, even if they are added to the “AB Suite Runtime Administrators” group. All users must have local administrator privileges to perform the deployment operations.

Refer to Command Line and Programmatic Access to Runtime in the *Agile Business Suite Runtime for Windows® Operating System Administration Guide* for more information about the user privileges.

Configuring Secure RATL

TLS protocol adapter provides a secure connection between the server and the client. A TLS certificate must be installed on the server to configure RATL TLS protocol adapter.

Perform the following steps to configure RATL TLS protocol adapter:

1. Get the digital certificate issued by a trusted third-party Certificate Authority (CA).
2. Install the certificate along with the chain of certificates in the server machine.
Perform the following steps to install the certificates:
 - a. Click **Start**, point to **All apps**, expand **Windows System**, and then click **Run**. Enter certlm.msc in the **Run** window. Alternatively, enter certlm.msc in the search box, and then press the **Enter** key.
 - b. To import the certificate into Certificates in Personal, expand **Personal** and select **Certificates**.
 - c. To import the chain of certificates into Trusted Root Certificate Authorities in Certificates, expand **Trusted Root Certificate Authorities** and select **Certificates**.
 - d. Right-click **Certificates**, point to **All Tasks**, and then click **Import**.
 - e. Click **Next** in the **Certificate Import Wizard**.
 - f. Browse to the path where the certificate that you want to install is located, and then click **Next**.
 - g. Click **Finish**.
A pop up is displayed to indicate that the import is successful.
Certificates are installed successfully.
3. Configure the properties of the RATL TLS protocol adapter using AdminTool. Refer to the *Agile Business Suite Runtime for Windows® Operating System Administration Guide* for more information on configuring the protocol adapter.

Adding Registry Keys for TLS 1.3

RATL TLS protocol adapter can use TLS 1.3 version for secure connection.

Note: *TLS 1.3 is an experimental version and is not recommended for use in a production environment.*

You must add registry keys to enable TLS 1.3. To add registry keys, perform the following steps:

1. Start regedit.exe.
2. Navigate to
[HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\SecurityProviders\SCHANNEL\Protocols\1.3]
3. Add the following registry keys:
[HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\SecurityProviders\SCHANNEL\Protocols\1.3\Server]
"DisabledByDefault"=dword:00000000
"Enabled"=dword:00000001
4. Select **OK** and close regedit.exe.

Other Security Considerations

Protecting Your Network Traffic

Since Runtime does not enforce network security, except between the Runtime components themselves, it is recommended you adopt some kind of protection for your information transfers. There are a number of technologies available to protect network traffic, such as IPSec, TLS 1.2, and TLS 1.3.

Deployment

Since the deployment packages are installed in the context of the deploying user, this user must be an administrator on the machine on which the deployment packages are to be installed.

Remote Deployment

It is important that the user be in at least a Windows domain and the user's account not to be marked as "Account is sensitive and cannot be delegated".

Debugger

Debugger requires access to the database in order to run.

If a user is not an administrator of the remote server machine, security configuration is required for the COM+ Security Helper application. All the users using debugger must be part of Secure Users role of Security Helper on the database server. To do this, add all the users to the Debugger Users group. This setting is required when the database server is installed in a separate or in the same remote machine with developer. Users can be added to COM+ roles using the Component Services MMC snap-in.

Runtime Setup

Before you generate an application to a Runtime environment, there are several setup requirements that must be completed. You need to:

- Add a runtime server
- Add a database server registration
- Add a database
- Install the Report Output Control System (optional).

Each of these requirements can be completed using the Runtime Administration tool, with the exception of the installation of the optional Report Output Control System. Refer to the *Runtime Administration Tool Online Help* for more information.

Clustering AB Suite Runtime

Applications generated using AB Suite are not inherently cluster-aware; however, they can be configured to function like cluster-aware applications using the Microsoft Windows Server 2019 Cluster management software along with SQL Server 2019 Failover Clusters. AB Suite supports the SQL Server 2019 AlwaysOn group, which enables a “High Availability” (HA) environment.

Nodes

A cluster comprises of machines or nodes connected to each other. The Cluster software monitors the processes and services running on each Node. The Node that runs a process or service is called the Active Node. The Passive Nodes do not simultaneously run the same process or service. If a Node unexpectedly fails or is intentionally taken down, the Cluster software ensures that the clustered processes and services from the failed Node are switched to another machine in the cluster, where they can restart and continue. This process is referred to as a **failover**.

Virtual IP Address/Network Name

One of the key capabilities of a failover cluster is the elimination of the need for the end user to know which machine or Node is currently active. The cluster management software achieves this with a floating virtual IP Address depending on which machine is the active Node. In AB Suite Windows Runtime, you only need to enter the virtual network name or IP Address of the cluster to access a particular service or process.

Resources

Application services, virtual IP Addresses, machine names, shared storage and devices that are monitored by the cluster management software are called Resources. Related resources are generally grouped together into Resource Groups for easier cluster management.

Dependencies

Some resources need other resources to run successfully. The relationships between resources are known as Dependencies. Dependencies are used to define how different resources relate to one another. These interdependencies control the sequence in which the cluster management software brings resources online and takes them offline.

AB Suite Application and Database Layers

AB Suite provides the optional ability to separate the application layer from the database layer. This allows the Database and Application to reside on different machines. Hence clustering for AB Suite can consist of two separate components, the Application layer and the Database layer. The exact cluster configuration varies as per requirements. You need to create a Resource Group for AB Suite if you use a separate cluster for the Application layer. Otherwise you can have a single cluster where both AB Suite and SQL Server are a part of the same Resource Group and so will fail over together.

Cluster Resource Group Setup

A cluster Resource Group should exist before setting up the various resources for AB Suite. To set up a separate Application layer cluster, a specific AB Suite Resource Group with its own IP Address and network name is needed. Alternatively it is possible to assign the resources to the SQL Server cluster Resource Group.

In the AB Suite Runtime environment, files such as the log file and the configuration file are created and updated. You must ensure that such files that change are always available regardless of the active Node. You can achieve this by defining shared disk resources. For example, the DATA folder that contains the log and configuration file must be assigned to a shared disk resource during installation.

You can do this post installation by changing the registry entries for:

`HKLM\Software\UNISYS\AB Suite\8.0\SM Runtime`

or

`HKLM\Software\Wow6432Node\UNISYS\AB Suite\8.0\SM Runtime`

if running 64-bit

The 3 keys to update are DataFolder, PrivateFolder, and PublicFolder.

It is also recommended that the application be deployed to a shared disk resource.

AB Suite Runtime Software Installation in a Cluster

Note: The AB Suite software installation requires that a Microsoft Cluster be created and that a SQL Server environment exists either in the cluster or in a separate cluster environment.

Since AB Suite applications are not cluster-aware, you have to manually ensure that the same options and configurations are used on each node in the cluster.

To install the basic AB Suite Runtime software, perform the following:

1. Install **AB Suite Runtime**.
2. Configure AB Suite protocol adaptor resources.
3. Define a generic script resource monitor.
4. Set up dependencies.

Installing AB Suite Runtime

It is important to create and add domain level Application and Admin user accounts. The AB Suite Application Admin user should be added to the local Administrators group of each Node prior to installation.

To enable AB Suite to install and function correctly in a clustered environment, the database components reside on the runtime server and not on the database server. The Database Server is identified by a virtual IP Address of the SQL Server cluster.

Before installation, select a Node and ensure that the shared disk resource for the Data folder is online. Perform a custom installation pointing to a local disk location for the software installation folder. Ensure that this location is available on all Nodes.

After installation, start the “Services” MMC plugin from **Administrative Tools > Services** and change all the AB Suite services to a start type of “Manual”. You can then move the shared disk resource to the next Node and repeat the process ensuring that the same locations are used for the installation and the Data folder, etc.

Configuring AB Suite Protocol Adaptor Resources

You need to create resources for each of the protocol adapters after installing AB Suite Runtime. At a minimum, this is the **AB Suite RATL TCP/IP protocol adaptor** and **AB Suite RATL TLS TCP/IP protocol adaptor**, but it could also include HUB, RATL MSMQ or the SOAP protocol adaptors.

To create a resource for a protocol adapter, perform the following:

1. Start the Server Manager MMC plug-in, and expand **Features, Failover Cluster Manager, Machine name**, and the **Services and applications** node.
2. Right-click the required Resource Group, and select **Add a resource, Generic Service**.

The **New Resource Wizard** appears.

3. Select the required Protocol Adapter.
4. Click **Next** on the subsequent screens to create the resource.
5. Click **Finish** after adding the required protocol adapters to the resource group.

Defining a Generic Script Resource

The Failover Cluster software provides a **Generic Script Resource** that is used to monitor and perform a clean-up or preparation of the cluster when a failover occurs. The Generic Script resource is a VB script with several predefined functions that are called depending on the state of a resource. For example, **Online**, **Offline**, **IsAlive**, etc. In the event of a failover of an AB Suite application, all the COM+ services are stopped and the status of the AB Suite applications is set to STOPPED. The ABSClusterMonitor.VBS script is used to monitor and call a standalone executable (ShutdownABS.exe) that shuts down all AB Suite COM+ services.

Note: Both the Sample Generic Script Resource VB Script and the standalone executable should be placed in the Data\Public folder. This is because the script and the executable expect to reside in this location, rather than it being a requirement of the Microsoft Failover Cluster software.

To add a generic script resource, perform the following:

1. Start the Server Manager MMC plug-in, and expand **Features, Failover Cluster Manager, Machine name**, and the **Services and applications** node.
2. Right-click the required Resource Group, and select **Add a resource, Generic Script**.

The **New Resource Wizard** appears.

3. Enter the location and name of the VB Script in the **Script file path** box.
4. Click **Next** to create the resource.
5. Click **Finish** after adding the required script to the resource group.

Note: If there are issues with the script, the resource fails to Add at this point. Check the Cluster logs via the "Cluster.exe" command line utility. The Log files are in the %windir%\Cluster\Reports folder.

Setting up Dependencies

Dependencies ascertain that the defined relations between resources ensure that resources are available in the cluster and in the correct sequence.

To create a dependency for a resource, perform the following:

To add a generic script resource, perform the following:

1. Expand the Resource group that holds the resource that needs to be updated.
2. Right-click on the resource and select **Properties**.
3. Select the **Dependencies** tab.
4. Click the line under the **Resource** column for the Resource list, and select a shared disk resource.
5. Click **OK** to add a dependency.

Adding a Runtime Server

The first step in setting up a runtime environment is to identify the servers to be used and add them to the Favorites folder for easy access. There are several ways in which to add a server to Favorites:

- Using the Domain and Network Neighborhood nodes, navigate to the required server. Once located, either:
 - Right-click the server node, select **All Tasks** and then **Send to Favorites**.
 - Drag and drop the server node to the Favorites folder.
- Alternatively, right-click the Favorites node and select **Add Server**. In the displayed dialog box enter the name of the required server and click **OK**.

Adding a Database Server Registration

Before you can add a database, you must set up the database server registration.

1. Right-click the required server node and select **All Tasks, Register Database Server**. The **Register DB Server** dialog box is displayed.
2. In the **DBMS registration alias name** field, enter a name to identify the database server registration.
3. In the **Server machine** field, enter the name of the database server. If the database is local, enter localhost. Otherwise, enter the remote database server name. If the database server is in a cluster, enter the database cluster name.
4. In the **Instance name** field, enter the SQL Server Instance name. If the SQL server instance on the database server is the default instance, leave this field blank.
5. Click **OK** to add the database server registration node to the runtime server node.

Adding a Database

Once you have added the database server registration you can start adding databases. There are two ways in which to add a database.

Creating a New Database

The Administration tool provides the functionality to create a basic database on the server. However, it is recommended that you create your own databases using the Enterprise Management tools that come with your database software. This has the advantage of enabling you to fully control the preparation, deployment, and configuration of the database.

To create a new database, perform the following:

1. Right-click the required Registration node, point to **New**, and then select **Database**.

The **Add a New Database** dialog box appears.

2. In the **Name** box, enter the name of the new database.

Note: You cannot use any SQL reserved keyword, such as *Select*, *Where*, *Break*, *Continue*, *From*, and so on as a database name. For example, if you use "Select" keyword as the database name, the following error message is displayed and the tool might crash:

"Select:- Incorrect syntax near keyword 'Select'"

Refer to MSDN documentation for more information on SQL keywords.

3. If you want the database to be Transparent Data Encryption (TDE) enabled:
 - a. Under Transparent Data Encryption Settings, select the **Enabled** check box.
 - b. From the **Encryption Algorithm** list, select the algorithm to be used for encryption.

Refer to the Agile Business Suite Runtime for Windows® Operating System Administration Guide for more information on enabling and disabling SQL TDE.

4. Click **OK**.

This adds a new database on the database server.

Attaching an Existing Database

To add an existing database, you must attach the database to the new Windows Runtime environment using the Administration tool. An existing database can be:

- A SQL server database.
- An AB Suite 5.0, 6.1, 7.0, or 8.0 runtime environment database.
- An AB Suite 5.0, 6.1, 7.0, or 8.0 runtime database to be used as new debugger database.
- An AB Suite 5.0, 6.1, 7.0, or 8.0 debugger database created by another user to be used as new debugger database.

To attach an existing database, perform the following:

1. Right-click the Database Server node and select **All Tasks, Attach Existing Database**.

The **Attach a Database** dialog box is displayed with a list of databases that can be attached.

Notes:

- The list includes AB Suite 5.0, 6.1, 7.0, or 8.0 runtime environment databases and existing SQL server databases.
 - Only the AB Suite runtime database names are appended with "(AB Suite)".
2. Select a database from the list.
 3. Click **OK**.

After attaching the database you can start the AB Suite system.

If you want to enable or disable TDE for the newly attached database, refer to the *Agile Business Suite Runtime for Windows® Operating System Administration Guide*.

Installing the Report Output Control System

The Report Output Control System (ROC) is an optional module, which you can install. You can browse or print reports using the Report Output Control system. When you start the ROC system, you temporarily leave your application. ROC is a separate system that controls report output for all applications within a given database.

To install the Report Output Control System, perform the following:

1. Use the Runtime Administration tool to add a Database Server Registration . Refer to [Adding a Database Server Registration](#) for more information.
2. Open the Command Prompt window as Administrator and use the Change Directory command to go to the <Installation Directory\ROC> directory. For example C:\program files\Unisys\...\Roc.
3. Run the ROC installation script "InstallRoc.js" contained in that directory, passing the Application User login name, the Application User password, and the Application User domain as parameters.

You can also provide following optional parameters:

- Target Database Server registration
- Target Database name

The syntax is

```
csript InstallRoc.js <Application-Users login-name>
<Application-User password> <Application Users domain>
[Target Database Server Registration] [Target Database Name]
```

For example:

```
csript InstallRoc.js AppUser App1User . NonDefault CustomROCD
```

Note: The "." period in the example signifies the local machine as a domain.

When the script runs, it performs the following actions:

- a. Checks if you have a registration called “default” or a name passed as Target Database Server registration. If the registration is not found, the script displays an error.
- b. Creates a database called “ROCDDB” or a database with a name passed as Target Database name, if you do not already have one.
- c. Installs ROC from a RocSystem.msi, after the installation of the Report Output Control System is completed successfully.
- d. Deploys ROC and displays a message after a successful deployment.

Alternatively, if you have specified Target Database Server registration and Target Database name in the Runtime Administration tool, you can use the DeployPackage Runtime API to install ROC system.

For example, the following command run from a command prompt as an Administrator, installs ROC System under a “NonDefault” Database Server registration with “NewROCDDB” as its Runtime Database.

```
DeployPackage /L <Absolute path of RocSystem.msi> /U <Application User Login Name>  
/P <Application User Password> /TSN localhost /TDBR NonDefault /TDBN NewROCDDB
```

Database Configuration

The Runtime Administration tool provides the basic facilities for creating and configuring SQL Server database. However, it is recommended that databases be created and configured using the Enterprise Manager tools that are provided with the database software. This provides far greater control and flexibility over the configuration and administration of your databases.

Detaching a Database

Detaching a database involves the removal of all Agile Business Suite related tables and constructs from the specified database.

To detach a database using the Administration tool, right-click the required database node and select **All Tasks**, then **Detach From Runtime**.

This process does not delete the database.

Deleting a Database

The Administration tool can only be used to delete databases that were created using the Administration tool. Databases created using the database software must be deleted with the Enterprise Manager tools of the database software.

To delete a database using the Administration tool, right-click the required database node and select **Delete** from the context-menu.

When deleting a database, the database is checked to ensure there are no resident applications. If applications are still present, the database cannot be deleted. If there are no applications, but tables still exist, the database is detached and then deleted.

Section 8

Runtime for ClearPath MCP Installation and Configuration

This section describes the installation of Agile Business Suite Runtime for ClearPath MCP Operating System.

Notations

Where specific operating command strings are given, italics are used to delimit metatokens or variables. Enter an actual value in place of these variables as instructed. Square brackets delimit optional values.

Pre-Installation Requirements

Products and Terminology

This subsection gives a summary of the main Agile Business Suite Software products.

This subsection lists important terminology. Read this subsection carefully to help you understand how the instructions in this document relate to your particular type of software.

Runtime

Runtime is the term used for the programs and utilities needed to run deployed applications.

Deployed applications, Reports, and Networks cannot run on your host equipment until Runtime is installed.

Transferring an Application

Runtime Transfer – The Runtime Transfer utility enables built applications to be transferred to and from other MCP environments.

Configure – The Configure utility is used to install and configure an application from a magnetic tape or a directory of files produced on a different host.

Considerations

When transferring an application built under release 8.0 to another MCP based host, you must also use Runtime from release 8.0 on the target host.

Refer to the *Agile Business Suite Runtime for ClearPath MCP Administration Guide* for more information on transferring applications.

Required System Software Requirements

This subsection lists the required and the optional software for Agile Business Suite 8.0 Runtime for ClearPath MCP operations. Install the software according to the instructions included in the documentation for each item.

Caution

Using system software facilities to manipulate message content outside of functionality (for example, COMS PIs) is done at your own risk.

General Software Requirements

Agile Business Suite 8.0 Runtime for ClearPath MCP supports System Software Release 60.0 and 62.0, including:

- COBOL85 (Note that COBOL74 cannot be used.)
- DMS II and DMSII XE

DMSII XE requires Extended Edition. If you are using Extended Edition features, you must have a license for Extended Edition.

- DMS/INQUIRY (optional)
- ERGO (optional)
- SYSTEM/CANDE
- SYSTEM/BINDER
- COMS
- DMALGOL
- Multi Lingual System (MLS)
- NEWP compiler

To interface with the ADDS Dictionary, the ADDS software must be installed.

MCP Releases Supported in this Release

Release	Qualification EPSILON (LEVEL5)	Qualification ETA (LEVEL6)	ALGOL IC Level for DUMPINFO Compatibility
MCP 20 (SSR 62.0)	Supported	Qualified	MCP 62 [62.080.000]
MCP 19 (SSR 60.0)	Supported	Supported	ALGOL-060.0A.10

MCP Runtime Compatibility Matrix

Use this matrix to select an installation package for MCP Runtime.

AB Suite MCP Runtime Package	MCP Architecture ETA COMPILETARGET LEVEL5	MCP Architecture ETA COMPILETARGET LEVEL6
EPSILON - LEVEL5 code files	Compatible (MCP 19, 20)	Compatible (MCP 19, 20)
ETA - LEVEL6 code files	Incompatible	Compatible (MCP 19, 20)

Note: Check the setting of the *COMPILETARGET* option on your host. If it is set to *LEVEL5*, do not use the *ETA* package.

Caution

Although the ETA package has undergone full engineering testing, it is highly recommended to perform a complete regression test before using the ETA LEVEL6 package in production.

MCP Runtime will discontinue support for LEVEL5 code files in AB Suite 9.0.

From AB Suite 9.0, MCP Runtime will release one package, which will support LEVEL6 code files.

Caution

For those who use Runtime Transfer, be aware that the LEVEL6 code files are incompatible with the EPSILON architecture. If your production machine has the EPSILON architecture, do not build the source system, for the transfer, with the ETA package. The LEVEL6 code files that are transferred to the machine with the EPSILON architecture does not run.

Minimum Software IC Levels for MCP 19 (SSR 60.0)

Software	IC Level
MCP	MCP-060.0A.21
COBOL85	COBOL-060.0A.10
ALGOL	ALGOL-060.0A.10
BINDER	BINDER-060.0A.3
DMSII	DMSII-060.0A.14
OLEDB	OLEDB-060.0A.1

Note: The minimum IC level specified for COBOL is mandatory.

Minimum Software IC Levels for MCP 20 (SSR 62.0)

Software	IC Level
MCP	MCP-062.0A.12
COBOL85	COBOL85-062.0A.5
ALGOL	MCP 62 [62.080.000]
BINDER	MCP 62 [62.080.000]
DMSII	DMSII-062.0A.4

Note: The minimum IC level specified for COBOL is mandatory.

Network Software Requirements

To support cross-host transactions, networking capability is required.

If you do not require cross-host communications, then local port capability is provided by LPPSUPPORT.

If you require cross-host communications, BNA V2, TCP, or OSI are required.

If you require interhost system services (for example, file transfers), you must also install Distributed System Services (DSS). You need to install this if you are going to use the Agile Business Suite Builder or the Remote Subroutine Server.

If you require Agile Business Suite Debugger to call subroutines on the host, you must install the Remote Subroutine Server (also known as LRSS) in addition to DSS. Refer to [Installing and Configuring Remote Subroutine Server](#).

If you intend to use Enterprise Output Manager for printing Reports, then you need to install and configure the Enterprise Output Manager software for the MCP based hosts. This enables the MCP based applications to direct print output to the Enterprise Output Manager PC Server when the default output device is set to DP. Refer to the *Enterprise Output Manager* documentation for more information on installing and configuring Enterprise Output Manager on the MCP based host.

Other Software Release Compatibility

The following software release compatibility is required:

- Developer
 - Agile Business Suite Release 8.0 supports Case Interchange File (LCIF) interchange with Enterprise Application Developer 3.3, and Agile Business Suite 2.0, 3.0, 4.0, 5.0, 6.1, 7.0, and 8.0.

Minimum Hardware Requirements

The following hardware is necessary to use Agile Business Suite 8.0 ClearPath MCP based software:

- MCP based mainframe, with a minimum of 50 Megabytes of memory. Agile Business Suite 8.0 is compatible with all MCP based platforms that are currently supported by Unisys.
- Unisys T27 emulators and WebEnabler
 - Refer to [Configuring Terminal Devices for Runtime for ClearPath MCP](#) for more information.
- Line printer (optional).
- Disk space. Sufficient to support the minimum disk requirements shown in the following table (based on release 8.0 configured with default settings and using a secondary audit file).

Files	Sectors	Description
NGEN29/=	217000	Skeleton files and general utilities common to all applications.
Other Files	18000	Other database files and COMS Configuration File

Runtime for ClearPath MCP Installation and Configuration

Files	Sectors	Description
Total	1061000	

In addition, the following table shows the requirements needed on DISK. These files are shared by all end-users on the host.

Files	Sectors	Description
NGEN29/=	32000	Shared files and programs
Others	250	EXAMINER and LINCXSUPPORT files

As disk and memory requirements vary, contact your Unisys representative for planning assistance.

Setting Up the Host

Before you install and configure your software, you should perform the following tasks:

- Set the Host Name for your system.
- Ensure SYSTEM/BINDER, SYSTEM/DASDL, SYSTEM/DMALGOL, and SYSTEM/COBOL85 are accessible for your usercode.
- Ensure that the SSR level of the compilers and DMSII software that are installed on your machine for AB Suite builds is supported by AB Suite MCP Runtime.
- If configuring with a Dictionary or Work pack that is the alternate family for the usercode under which you run the configure option. Then, before the configure job is run, change the usercode family to:

`DISK = alternate ONLY.`

This ensures the appropriate files are copied to the correct pack.

- Ensure that an SL command has been performed on the library KEYEDIOIISUPPORT on your system. Setting the KEYEDIOI is recommended but not required.

Configuring Terminal Devices for Runtime for ClearPath MCP

COMS Station Definitions

COMS station definitions, as used by Agile Business Suite Runtime for ClearPath MCP, make use of fields within COMS Installation Data entities. The use of these fields is shown in the following table.

Field	Usage	Description
Integer1	Station type	0 = ET/TD/T27

Field	Usage	Description
		1 = ET/TD/T27
		4 = NOFORM interface
Integer2	Access level	0 = Standard
		1 = ODT
		2 = Controller
Integer3	Privilege level	1 – 15
String1	Associated printer	First 17 characters
	Model	Characters 18 – 34
String2	Default language	Language name, up to 15 characters

Notes:

- If Integer1 is equal to 0 for a station, when Agile Business Suite receives a BYE from that station, a ?CLOSE request is sent from the station.
- When Integer1 is equal to 1, Agile Business Suite performs a programmatic CLOSE of the window.
- If the Integer3 value for your station is less than the user privilege level for an Ispec (as set on the Component/Event Choices screen), you will see the error message:
`Insufficient privilege for ispec`
when you try to access the Ispec from your station.
- Printers must have IDs in order to define Models.

If you have external applications that use Installation Data entities, and these conflict with the way in which Agile Business Suite Runtime for ClearPath MCP uses these entities, you should define your non-external entities as secondary Installation Data, and then associate this secondary Installation Data with the primary.

Configuration Settings for Terminals Qualified for Agile Business Suite Runtime for ClearPath MCP

Refer to terminal device reference material for more information on configuration. The required register settings for terminal devices are given in the following subsections (by device type). The convention XX XX represents a unique terminal address (in hexadecimal).

General Requirements

When defining terminal devices:

- Do not use braces as alternate forms characters.
- Agile Business Suite Runtime for ClearPath MCP requires terminals capable of displaying a 72-character status line.

Runtime for ClearPath MCP Installation and Configuration

- Where applicable, configure your terminal so that carriage returns are not visible.

TD 830 and TD 830J (9600 BPS TDI)

Location	Hex Settings
0080	0A FB 01 00 17 4F 1F 1E 10 XX XX 04 09 00 04 04
0090	00 2F 4F 17 4F FF 00 4F 17 40 00 08 03 50 0F FF
00A0	04

MT 983/5 (9600 BPS TDI), level 3 firmware

Location	Hex Settings
0080	0A A1 01 03 17 4F 1F 1E 10 XX XX 47 08 01 47 41
0090	00 2F 4F 17 0F 00 00 4F 17 00 00 08 00 00 07 80
00A0	04

SR-100 and SR-110

Datacomm	Setting
Databits	7
Parity	E
Syn	N
60 Hz	Y
2 Stop Bits	N
ACK Level	0051
XMIT #s	N

Edit	Setting
Stay in receive	Y
Forms XMIT to cursor	Y
SOH Exits Forms	Y
SOH Clears Page	N
Auto Page Adv Enable	N
DC1=Stay In RCV	Y

Edit	Setting
DC2=Toggle Forms	Y
Dcom LF->CR	N
Dcom CR->LF	Y
ETX Plant From Dcom	N
CR Plant From Kbd	N

ET 1100 and T 27 Terminal/Emulator Configuration Menu

Option	Value
LINE/Page	24
CHAR/Page	80
LINE/SCREEN	24

To print on AP 1312 or AP 1314 terminal printers from an ET 1100, the PRINT GROUP options must be set to the default values, with the following exceptions:

Option	Value
BITS/CHAR	7
AUX INPUT	D
BUSY (I/O)	1
SPECIFY KEY	A

In addition, the following values must be set.

Option	Value Required
SCREEN	17280 (max)
ALT FORM DELIMITERS OPEN (US)	1F
CLOSE (RS)	1E
PRINT AUX	2-character address of background printer
PRINTER DCOM	2048 (min)
PRINT BPS	Must be set as relevant for particular printer

TC 4000J

On switch SW734, bits 4 through 8 (inclusive) must be closed.

Installing and Configuring Runtime for ClearPath MCP

Preparing for Installation

Before commencing installation, read [Pre-Installation Requirements](#) and [Installation Checklist](#).

In addition, it is important that you read your Agile Business Suite 8.0 Runtime for ClearPath MCP Software Release Announcement (SRA) before commencing installation. You must note carefully any listed conditions or restrictions that might apply to you.

Installation Checklist

Use this checklist when considering the issues and the steps you must take before and after you install your software. (Unless specifically stated otherwise, references in the table are to topics later in this section).

If you are already a user, you only need to confirm that your current pre-installation setup is correct before migrating to this release.

Step	Action	References
1	Review the Agile Business Suite terminology and product range	Products and Terminology
2	Verify that you have the correct release media	Required System Software Requirements
3	Verify that you have the necessary hardware	Minimum Hardware Requirements
4	Verify that you have the necessary software	Required System Software Requirements
5	Check your host setup.	Setting Up the Host
6	Ensure that your terminal device configurations are appropriate for Agile Business Suite.	Configuring Terminal Devices for Runtime for ClearPath MCP
7	If you are already a user, consider any relevant conversion issues.	Migration Procedure
8	Installing the software.	Installing the MCP Runtime Software

Step	Action	References
9	Verify that you have the appropriate COMS configuration for your site requirements.	Configuring COMS for Applications

General Notes About Installation

Before initiating the installation process, you should be aware of the points outlined in the following subsections.

Setting Up Tasklimits

When configuring software, the Configuration WFL job might terminate because the number of spooled tasks exceeds the Tasklimit for the queue. You can avoid this happening by submitting the Configuration WFL to a queue that does not have the Tasklimit attribute set. The maximum value of the Tasklimit is 31.

Required Supplementary Files

The following files are copied to DISK (or the alternate family pack), provided that the version being installed is higher than the version currently in place. (If it is not, the files are not copied from the Dictionary specified during installation, and a message is displayed.)

- *NGEN29/1/LIBRARY
- *NGEN29/1/LTEACH
- *NGEN29/MLSLIBRARY
- *NGEN29/1/HUBROUTER (copied to same pack as COMS)
- *NGEN29/UTILITY/LINCFORM
- *NGEN29/GLI
- *NGEN29/OFF
- *NGEN29/LVU
- *NGEN29/RIP
- *NGEN29SYS/CODES
- *EXAMINER/LIBRARY
- *SYSTEM/LINCXSUPPORT

Using a Privileged Usercode for Installation

The usercode from which the RUNTIME job is started must be privileged. If the RUNTIME job is started from a non-privileged usercode, any SLs for libraries released with this cut must be done manually from MARC under a privileged usercode.

If your machine has Security Administrator status enforced (by enabling the SECADMIN option), the usercode from which the RUNTIME job is started must have SECADMIN privileges. If the usercode does not have SECADMIN privileges, any SLs for libraries released with this cut must be done manually. Therefore, you must decide which usercode to use before you begin the installation.

Runtime Transfer Considerations

If you are installing AB Suite on environments used in Runtime Transfers, you must install the release from the same installation package in both the source and the target runtime environments.

Installing multiple Runtimes on the same MCP host

If you are installing multiple Runtimes on the same MCP host, each installation must be installed under separate usercodes with different APPL_BLD identities and unique port numbers. Each installation of Application Builder (APPL_BLD_) requires its own runtime environment. More information on installing APPL_BLD can be found in the installation instructions.

Installing the Authenticate File

If this is the first time that the runtime is being installed in the designated runtime usercode and you have not installed the GCA release already, you must install the authentication file now.

The release media contains two packages.

1. EPSILON package with LEVEL5 code files.
2. ETA package with LEVEL6 code files.

See [Required System Software Requirements](#) to view the MCP Runtime Compatibility Matrix. The MCP Runtime Compatibility Matrix helps you to choose the package that is compatible with your MCP host architecture and MCP release. When you choose a package from the IC release, ensure that it is compatible too.

Follow these steps to install the authentication file:

1. Copy the GCA release to Windows and mount the ISO image file.
 - EPSILON: GCA-80-1000-02.CON
 - ETA: ETA-GCA-80-1000-02.CON
2. Copy the GCA container file from the ISO image to the MCP host. Select the container with the package you want to install.
3. From CANDE, unwrap the authentication file to the runtime usercode and runtime pack:

EPSILON

```
WFL UNWRAP *GCA/80/1000-02/NGEN29/AUTHENTICATE AS
(<Runtime Usercode>)NGEN29/AUTHENTICATE
OUTOF "GCA-80-1000-02.CON"
To <Runtime Pack>(RESTRICTED = FALSE)
```

ETA

```
WFL UNWRAP *ETA/GCA/80/1000-02/NGEN29/AUTHENTICATE AS
(<Runtime Usercode>)NGEN29/AUTHENTICATE
OUTOF "ETA-GCA-80-1000-02.CON"
To <Runtime Pack>(RESTRICTED = FALSE)
```

Copying the Runtime Install Job from the Release Media

The release media contains two packages.

1. EPSILON package with Level5 code files.
2. ETA package with LEVEL6 code files

See [Required System Software Requirements](#) to view the MCP Runtime Compatibility Matrix. The MCP Runtime Compatibility Matrix helps you to choose a package that is compatible with your MCP host architecture and MCP release.

To copy the MCP Runtime install job from the release media, perform the following:

1. Copy the IC release to Windows.
2. Map a network drive to your privileged usercode on the MCP host.
3. Copy the IC container file to the MCP host. Select the container with the package you want to install.

EPSILON: IC-80-<IC Number>.CON

ETA: ETA-IC-80-<IC Number>.CON

4. Disconnect the network drive.
5. From CANDE, unwrap the container file:

EPSILON

```
WFL UNWRAP *= OUTOF "IC-80-<IC number>.CON"  
TO <Transfer pack> (RESTRICTED=FALSE)
```

ETA

```
WFL UNWRAP *= OUTOF "ETA-IC-80-<IC number>.CON"  
TO <Transfer pack> (RESTRICTED=FALSE)
```

6. Download the install WFL:

EPSILON

```
COPY (TRANSFER) IC/80/<IC number>/NGEN29/WFL/RUNTIME  
AS NGEN29/WFL/RUNTIME  
FROM <Transfer pack> (PACK)
```

ETA

```
COPY (TRANSFER) ETA/IC/80/<IC number>/NGEN29/WFL/RUNTIME  
AS NGEN29/WFL/RUNTIME  
FROM <Transfer pack> (PACK)
```

Installing the MCP Runtime Software

Note: If you are installing to environments used in Runtime Transfers, you must install the release from the same installation package in both the source and target runtime environments.

To install the MCP Runtime Software, perform the following:

1. Logon to your privileged usercode.
2. Start the Runtime WFL, by entering:

```
START NGEN29/WFL/RUNTIME
("usercode","pack","aliaspack",
  IC media parameter )
```

The *usercode* value is the usercode to which the Runtime is installed, which might be an asterisk (*).

The *pack* value is the family name of the pack to which the Runtime is installed, which might be *DISK* or *altpack*.

The *aliaspack* value is the pack for your station alias file. Refer to the *Agile Business Suite Runtime for ClearPath MCP Administration Guide* for more information on station aliases.

IC media parameter = "MD=*MediaDirectory* MN=*MediaName* N=*Cut#*"

MediaDirectory is the directory containing the installation files:

EPSILON

(TRANSFER)IC

ETA

(TRANSFER)ETA/IC

MediaName is the name of the pack on which the installation files are located.

<Transfer pack>

Cut# is the IC cut number for the release.

<IC number>

For example:

"MD=(TRANSFER)ETA/IC MN=TFRPACK N=1000-01"

Notes:

- *The usercode from which the RUNTIME job is started must be privileged.*
If the RUNTIME job is started from a non-privileged usercode, any SLs for libraries released with this cut must be done manually from MARC under a privileged usercode.
- *If your machine has Security Administrator status enforced (by enabling the SECADMIN option), the usercode from which the RUNTIME job is started must have SECADMIN privileges.*
If the usercode does not have SECADMIN privileges, any SLs for libraries released with this cut must be done manually.

3. License Agreement – Before the installation begins, you will be asked to accept the license agreement. The installation job is suspended twice to allow you to read the license information. The terms of the license agreement might be found in the instruction blocks. Enter ?<mix> IB nn from MARC to view each instruction block. Enter ?<mix>OK to accept the license agreement and install Agile Business Suite 8.0 for the MCP Operating System.

4. During the installation, you will be prompted:

```
** DO YOU WISH TO OVERWRITE EXISTING LIBRARIES (HUBROUTER, RATL, ETC.) WITH THE  
LIBRARIES IN THIS RELEASE?  
AX YES TO OVERWRITE OR AX NO TO INSTALL/RETAIN LATEST VERSION **
```

This allows you to overwrite existing libraries, even if their release level is higher than the GCA release.

Respond with AX YES to overwrite existing libraries.

Respond with AX NO to allow the installation job to use release checking and only install the new libraries if they have a higher release level than the existing libraries.

5. During the installation, you will be prompted to confirm the version of AB Suite 8.0 MCP Runtime that is being installed.

Respond with OK to confirm.

DS the job to terminate the installation.

6. If you have not already installed the GCA release, or the authenticate file, you will be prompted with the following messages:

```
>>> (<usercode>)NGEN29/AUTHENTICATE ON <pack> IS MISSING OR INVALID  
<<<
```

```
COPY VALID AUTHENTICATE FILE FROM THE GCA RELEASE: AX TO CONTINUE  
OR DS
```

When these messages appear:

- Copy the valid authenticate file from the GCA release to (<usercode>)/NGEN29/AUTHENTICATE ON <pack> and respond with **AX** to continue with the installation. Refer to Installing the Authenticate File for instructions on retrieving the authenticate file.
- Respond with DS to terminate the installation

Note: These messages cannot be translated because *MLSLIBRARY* may not have been installed yet.

7. During the installation, you will be prompted for the SSR level of the LOGIC and DUMPINFO files to be installed. The SSR level must match that of the DMALGOL compiler currently installed on your system. You will be prompted to respond to the waiting entry with one of the following:

EPSILON

600, 620, YES

ETA

600, 620, YES

The meanings of these are:

Runtime for ClearPath MCP Installation and Configuration

Response	Meaning	Compatible with DMALGOL compiler	MCP Release
600	Install 600 LOGIC and DUMPINFO files	IC ALGOL-60.0A.10	MCP 19 or 60.0
620	Install 620 LOGIC and DUMPINFO files	MCP 62 [62.080.000]	MCP 20 or 62.0
YES	Install the LOGIC files for the corresponding, supported MCP SSR		

If you respond with YES and your MCP release level is not supported, you will be prompted to enter the SSR level of a DMALGOL compiler that is installed on your system and is supported.

If you respond with YES, or with the SSR level of your MCP release, and you see the following message, you must choose a DUMPINFO file that is compiled with a specific ALGOL IC release.

"THE SELECTED DUMPINFO FILE IS NOT COMPATIBLE WITH THE CURRENT
DEFAULT DMALGOL VERSION."

"PLEASE CHECK FOR OTHER DUMPINFO FILES UNDER
(RTUSER)NGEN29/LOGIC/DUMPINFO/= ON RTPACK"

The message indicates that the default DUMPINFO file for your MCP release level is not compatible with the DMALGOL compiler installed on your MCP server.

To look at DUMPINFO files that are available to you, enter the following command from CANDE:

FILE (RuntimeUser)NGEN29/LOGIC/DUMPINFO/= ON RuntimePack

Where, *RuntimeUser* and *RuntimePack* are the usercode and pack on which the runtime is being installed.

You may see a list similar to this one:

FILE (RTUSER)NGEN29/LOGIC/DUMPINFO/= ON RTPACK

(RTUSER) ON RTPACK

. NGEN29

.. LOGIC

... DUMPINFO : INFOFILE

... DUMPINFO

.... 600 : INFOFILE

.... 620 : INFOFILE

.... 600A4 : INFOFILE

.... 600A8 : INFOFILE

.... 600A9 : INFOFILE

The default DUMPINFO files have the MCP SSR number as the last node in the filename. DUMPINFO files compiled with a specific release of the ALGOL compiler will have the IC number as the last node of the filename. If you are using MCP 19/60.0, and you currently have DMALGOL-060.0A.8 installed, enter 600A8 when prompted to enter the SSR level of the LOGIC and DUMPINFO files to be installed.

If you cannot find a DUMPINFO file that is compatible with the DMALGOL compiler that is currently installed, choose a DUMPINFO file and follow the instructions to continue the installation. Afterwards, install an ALGOL IC that is compatible with one of the available DUMPINFO files, or submit a Service Request.

If you want to use a different set of compilers to the default compilers, select the DUMPINFO file that is compatible with the DMALGOL compiler of the alternate set and modify the TASKSTRING attribute of NGEN29SYS/BLD with the location of the compilers, after the IC installation is complete

```
WFL MODIFY (<Runtime Usercode>)NGEN29SYS/BLD ON <Runtime Pack>;  
TASKSTRING= "[Tparam,]<compiler list>";
```

Where <Tparam> is T=5.

Include this if you are installing the EPSILON package on a host with the ETA architecture.

Where <compiler list> is

```
C=<COBOL85 compiler>, D=<DMALGOL compiler>, B=<BINDER>
```

For example,

```
WFL MODIFY (RTUSER)NGEN29SYS/BLD ON RTPACK;  
TASKSTRING= "T=5, C=*COBOL85/600, D=*DMALGOL/600, B=*BINDER/600";
```

or

```
WFL MODIFY (RTUSER)NGEN29SYS/BLD ON RTPACK;  
TASKSTRING= "C=(MYUSER)COBOL85/600 ON MYPACK,
```

```
D=(MYUSER)DMALGOL/600 ON MYPACK, B=(MYUSER)BINDER/600 ON MYPACK";
```

8. During the installation, you will be prompted for the SSR level of the SMU, DMU and CFG codefiles to be installed. The SSR level must match that of the DMSII level of the application databases that are built by the runtime being upgraded. You will be asked to respond to the waiting entry with one of the following:

EPSILON

600, 620, YES

ETA

600, 620, YES

The meanings of these are:

Runtime for ClearPath MCP Installation and Configuration

Response	Meaning	MCP Release
600	Install 600 DAC, SMU, TRANSFER, DMU, and CFG files	MCP 19 or 60.0
620	Install 620 DAC, SMU, TRANSFER, DMU, and CFG files	MCP 20 or 62.0
YES	Install SMU, TRANSFER, DMU, and CFG files for the corresponding supported MCP SSR	

If you respond with YES and your MCP release level is not supported, you will be asked to enter a supported level of DMSII that is installed your machine.

If the systems that are deployed by this runtime environment use DMSII software located under a usercode and on a pack, as specified by DMSII Usercode and DMSII pack segment configuration properties in the configuration of the segment, the SSR level selected for SMU, DMU, and CFG should correspond to the SSR level of the DMSII software.

If there are AB Suite application databases of different DMSII release levels, some use 60.0 and some use 62.0, for example, it is strongly recommended that separate runtime environments should be created to handle the different levels. Designate one runtime for SSR 60.0 and one for SSR 62.0.

9. During the installation, you might be prompted to acknowledge that an updated version of MLSLIBRARY has been installed. Respond to the waiting entry with **OK**. If you use a language other than ENGLISH, check for untranslated messages in the file NGEN29/MLSLIBRARY/UNTRANSLATED.
10. During the installation, you will be asked whether you wish to install Application Builder.

You will be asked "DO WISH TO INSTALL APPL_BLD? AX YES/NO". You have the choice of installing the default Application Builder or a clone. If you wish to install either, respond with ?<mix#> AX YES, otherwise respond with ?<mix#>AX NO.

If you respond with YES, you will then be asked "DO YOU WISH TO INSTALL CUSTOM OR DEFAULT APPL_BLD? AX C FOR CUSTOM OR D FOR DEFAULT".

Installing Application Builder with Default Identity

Respond with ?<mix#>AX D if you wish to install the default Application Builder. This creates/modifies APPL_BLD_80.

Installing Application Builder with Custom Identity

Note: Each cloned Application Builder requires its own runtime environment. Each time you clone an Application Builder with a new identity, you need to install a new environment for it.

To install Application Builder with Custom identity, you need the following details:

<identity>	An identifier for the MCP Builder Server (limit of 6 characters). For example, 80A for APPL_BLD_80A. By default, the identity is 80 (for 8.0). You might choose an identity of up to six alphanumeric characters.
<port number>	A port file number from which to connect (this must be a unique number). By default, the port number is 8900. Do not use this number.

Respond with ?<mix#>AX C, if you wish to install a custom version of MCP Builder Server. Next, a message appears,

"PLEASE ENTER IDENTITY AND PORT NUMBER TO BE USED WITH CUSTOM APPL_BLD".

You are then prompted to enter the identity for the custom APPL_BLD:

"AX IDENTITY TO BE USED WITH CUSTOM APPL_BLD (MAX 6 CHARS)"

Respond with ?<mix#>AX <identity>

Next, you are prompted to enter the port number for the custom APPL_BLD:

Next, you are prompted to enter the port number for the custom APPL_BLD:

"AX PORT NUMBER TO BE USED WITH CUSTOM APPL_BLD"

Respond with ?<mix#>AX <port number>

Note: Nulls are not accepted. If you enter nulls for either, you are required to enter the identity and port number again.

After entering the identity and port number, you are asked to confirm what you entered:

"FOR CUSTOM APPL_BLD YOU ENTERED: ID=<identity>, PORT=<port>,"

IS THIS CORRECT? AX YES OR NO"

If it is correct, respond with ?<mix#>AX YES, otherwise respond with ?<mix#>AX NO and enter them again.

After Installing Application Builder

Check for waiting entries in the mix. You might need to respond to a request to initialize the APPL_BLD files. Respond to the initialization request with one of the following:

- Y to initialize a new APPL_BLD files.
- N to terminate APPL_BLD.
- C <file title> to convert an existing CPA file.

11. During the installation, you will be asked whether you wish to install RATL, LRSS, and TPTOMARC. If you wish to install either of them, respond with ?<mix>AX YES, otherwise respond with ?<mix>AX NO.
12. If you have installed an update to RATL during the installation, you must disable and enable RATLPCM to activate the new server.

```
NA CCF DISABLE PCM RATLPCM
NA CCF ENABLE PCM RATLPCM
```

13. Set up the required Support Libraries (SLs).

If you did not start the Runtime install job with adequate privileges for the SLs to be done automatically, set up the required Support Libraries (SLs) now.

If your host has Security Administrator (SECADMIN) status enforced, sign on to MARC with a SECADMIN status usercode. (Only a user/task/job with SECADMIN status might issue SL commands when SECADMIN status is enforced.)

From MARC, enter:

```
SL NGEN29SERVICES = *NGEN29/1/LIBRARY ON altpack
SL EXAMINERLIB = *EXAMINER/LIBRARY ON altpack
```

The *altpack* gives the alternate pack for the family of the usercode under which you are running Runtime. For example, your usercode family might be specified as follows:

```
DISK = INTPACK OTHERWISE SYSPACK
```

If so, enter *SYSPACK* as your *altpack* value.

Configuration of Runtime is complete. For your next steps, refer to [Configuring COMS for Applications](#).

UVMS: Setting up for Failover in a High Availability Environment

To prepare for failover, unwrap the contents of the IC container to disk and modify the constants in the LIB/INSTALL Parameters section of (<runtime usercode>)NGEN29/WFL/LIBS/INSTALL <runtime pack>.

1. Open (<runtime usercode>)NGEN29/WFL/LIBS/INSTALL ON <runtime pack>.
2. Modify the constants under LIB/INSTALL Parameters:

```
PRTUSERCODE = "<runtime usercode>"
PRTPACK = "<runtime pack>"
PICPREFIX = "(TRANSFER)IC" or "(TRANSFER)ETA/IC"
PMEDIANAME = "<Transfer Pack>"
PICNUMBER = "<IC number>"
PAPPLBLDID = "80"
PAPPLBLDPORT = "8900"
PINSTALLTEACH = "YES"
PINSTALLRATL = "NO"
PINSTALLLRSS = "NO"
PINSTALLTPTOMARC = "NO"
```

Mandatory changes:

PRTUSERCODE – MCP Runtime usercode

PRTPACK – MCP Runtime pack

PMEDIANAME – location of the IC installation files

Change the APPL_BLD ID if the runtime does not use the default port 8900

PAPPLBLDPORT

Change the APPL_BLD PORT number if the runtime does not use the default port 8900

PAPPLBLDPORT

Optional changes: set the ones to be installed to YES and set rest to NO.

PINSTALLTEACH

PINSTALLRATL

PINSTALLLRSS

PINSTALLTPTOMARC

3. Save (<runtime usercode>)NGEN29/WFL/LIBS/INSTALL ON <runtime pack>.

Configuring COMS for Applications

The Configure Utility automatically loads the COMS Configuration file for your software into COMS. You might override this automatic load by supplying a user-coded library, as described later in this subsection.

This automatic load does not apply to the COMS Stations file for new or changed Networks. You must manually load the COMS Configuration for NOF if required.

Note: *The COMS UTILITY window must be configured to support multiple active users, as the Auto-load process takes up one user slot. If the Maximum Users value is exceeded, the automatic load fails.*

Inhibiting or Interrupting Automatic Loading

The Configure Utility calls an entry point in a user-supplied library, and passes the COMS Configuration file name as a parameter. The library can programmatically verify and/or modify the parameter to allow or disallow the automatic loading.

Library File

The library file must be accessible under the file search path for the usercode under which you configured Agile Business Suite. The file is titled:

*NGEN29/USERLIB

If the library file is not found, or the library linkage fails, automatic loading proceeds.

Entry Point

The entry-point is *COMSVIFY*, defined as:

```
INTEGER PROCEDURE COMSVERIFY (COMS_LOAD_FILE_TITLE);  
EBCDIC ARRAY COMS_LOAD_FILE_TITLE [0];
```

The COMS_Load_FILE_TITLE parameter contains the title of the COMS Configuration file to be loaded. This file might be changed or replaced by a privileged process.

Return Values

The COMSVERIFY procedure should return one of the following values:

- The value 1 if the file is to be loaded.
- The value 0 if the file is *not* to be loaded.

Example

The following ALGOL procedure inhibits the automatic load for a user-coded application whose COMS Configuration file name begins with XX. Non-user-coded applications have COMS after the first slash (/) character.

```
$SET LIST  
BEGIN  
  INTEGER PROCEDURE COMSVERIFY (COMS_LOAD_FILE_TITLE);  
  EBCDIC ARRAY COMS_LOAD_FILE_TITLE [0];  
  BEGIN  
    % % Find out the system name:  
    % %  
    % % Take characters after the first slash (/):  
    % % - See if they start with "XX"  
    % % - If not, proceed with automatic load  
    % %  
    POINTER PA;  
    PA := COMS_LOAD_FILE_TITLE;  
    SCAN PA:PA UNTIL EQL "/";  
    % % Left pointing at the final "/"  
    PA := PA+1;  
    IF PA EQL "XX"  
    THEN  
      BEGIN  
        DISPLAY ("** COMS Autoload suppressed **");  
        COMSVERIFY := 0;  
      END  
    ELSE  
      COMSVERIFY := 1;  
    % %  
  END; % % of COMSVERIFY  
  % %  
  EXPORT COMSVERIFY;  
  FREEZE (TEMPORARY);  
END.
```

COMS Configuration for the SwitchTo Command

The SwitchTo command requires a COMS processing item such as TPTOMARC, to be installed for the MARCINPUT agenda in the COMS configuration data.

The TPTOMARC processing item is provided on your release media in the sample file:

NGEN29/SAMPLE/TPTOMARC/PROCITEM

Refer to the example of the TPTOMARC processing item in your COMS documentation for more information.

Installing and Configuring the Remote Access Server (RAS)

Introduction to Remote Access Server

The Remote Access servers can be used by Component Enabler to access applications.

The server-side deployment consists of a number of platform-specific Remote Access servers that handle communications between clients and applications. Clients and servers communicate, using RATL protocol running on TCP/IP. This protocol is a simple wrapping of a standardized and extended set of NOF messages that provide all the functionality needed to support GUI forms.

Clients establish normal sessions with applications through the Remote Access servers using a TCP/IP connection. These servers perform a number of checks, such as authenticating users and verifying the application exists, before granting the client access. The servers then receive transaction requests from client programs over a TCP/IP connection and pass them to the application. Transaction responses from applications are passed back to the clients over the same TCP/IP connection. Remote Access servers can also pass back asynchronous messages, such as messages from Reports, to a client application.

Remote Access servers can also use the Microsoft Message Queue (MSMQ) server for connections instead of TCP/IP connections.

The Remote Access servers are designed to offer connectivity, throughput, and transit times comparable to terminal access to the applications on the same host applications. Each client application runs independently of all other clients, with its own connection back to the application server. There are no points of single threading or possible congestion in the transaction path to add overheads or reduce performance.

Installing Remote Access Server

Codefile

The codefile is automatically installed to the CCF system pack.

CCF params file

- Obtain the sample CCF params file for the Remote Access Server, named:

(<ABSUITE usercode>)NGEN29/SAMPLE/CCF/
PARAMS/RATL ON <ABSUITE dictionary pack>

- Enter the Remote Access Entities required. Refer to CCF Configuration in [Installing and Configuring Remote Subroutine Server](#) for more information on configuring entities.

Runtime for ClearPath MCP Installation and Configuration

- Insert the definitions into the current copy of the CCF params file,

```
SYSTEM/CCF/PARAMS ON <CCF PACK>
```

Note: For A-Series Systems the CCF params file might not be present. Create this file using the sample provided:

```
(<ABSUITE usercode>)NGEN29/SAMPLE/  
CCF/PARAMS ON <ABSUITE dictionary pack>
```

COMS

Register the entities to COMS via the Utility window with the following file:

```
(<ABSUITE usercode>)NGEN29/SAMPLE/COMS/CONFIG/RATL ON <ABSUITE dictionary packruntime pack>
```

For Big Buffers, set the Maximum Message Text size for Global Activity to 65000.

CCF Configuration

Use the CCF components to configure the server entities as follows:

CCF Component	Entity
Router	PCM
CUCI	Device and Service
TCPIP	Port
RATL	Service, View, Language, MQserver, MQclient, and MQrequest

Router

Identify the server as a PCM to the router and enable it, using the following syntax:

```
Add PCM <name>  
  codefile = <filepath>  
Enable PCM <name>
```

Attributes	Description
<name>	Identifies a valid server name.
<file path>	Specifies the codefile path.

Example:

```
Add PCM <name>  
  codefile = <filepath>  
Enable PCM <name>
```

CUCI

As part of the CCF configuration you must configure a:

- Connection Device
- Connection Service

Connection Device

Configure a device to the CUCI PCM to associate device connection attributes with each dialog. Attributes are assigned using the following syntax:

```
Add Device <device name>
  acvt = <VTname>,
  ccenable = <boolean>,
  controlcapable = <boolean>,
  dynamic = <boolean>,
  marccapable = <boolean>,
  maxinput = <number>,
  maxoutput = <number>,
  messages = <category>,
  securitycatlist = <name>,
  ndlheader = <boolean>,
  screen = <boolean>,
  usage = <category>
```

Attributes	Description
<device name>	Defines a unique device name.
acvt	Specifies an Application Controller Virtual Terminal. This is the virtual terminal COMS expects the client to be using on input. This attribute is optional. <VT name> must be set to either Transparent or Default.
ccenable	Indicates if control character processing is enabled. This attribute is optional. This attribute can only be set to False.
controlcapable	Indicates if control commands can be entered or not. This attribute is optional. This attribute can only be set to False.
dynamic	Indicates if the connection is to be kept by COMS when the connection terminates. This attribute is optional.
marccapable	Indicates if the connection can handle screen output from MARC. This attribute must be set to True if you are to use the RATL Services attribute MARCOpenText .

Attributes	Description
maxinput	Specifies the maximum number of bytes in an input message. For Big Buffer Specs, this must be set to 45300 (65000 for Big Buffer Specs not using POF). <number> must be a minimum of 2500.
maxoutput	Specifies the maximum number of bytes in an output message. For Big Buffer Specs, this must be set to 45300 (65000 for Big Buffer Specs not using POF). <number> must be a minimum of 2500.
messages	Determines whether application messages are displayed at the client. <category> must be set to None.
securitycatlist	Specifies a COMS Security Category List configuration entity that is defined in COMS. When set, the value of this attribute is the default value used when connecting to COMS. It can be overridden by the service attributes of NOFidentity. This attribute is optional.
ndlheader	This attribute is optional. This attribute can only be set to False.
screen	Indicates whether the client is a screen device. This attribute is optional. This attribute can only be set to False.
usage	Identifies whether the client can receive input messages, send output messages, or both. <category> must be set to one of In, Out, or IO. The recommended value is IO, so that the client can both send and receive messages.

Example

```
Add Device RATLweb
  acvt = transparent,
  ccenable = false,
  controlcapable = false,
  dynamic = true,
  marccapable = false,
  maxinput = 10000,
  maxoutput = 10000,
  messages = none,
  securitycatlist = SCL_NOF,
  ndlheader = false,
  screen = false,
  usage = IO
```

Connection Service

Configure a service to the CUCI PCM to associate device connection attributes and to identify the connection path for each dialog. Attributes can be assigned using the following syntax:

```
Add Service RATLon
  closeaction = <number>,
  device = <name>,
  logoffdisconnect = <boolean>,
  dynamic = <boolean>
Enable Service RATLon
```

Attribute	Description
closeaction	The SYSTEM/COMS Close Action as defined on the SYSTEM/COMS Usercode menu. The close action is also defined on the Station menu of the COMS Utility. You must enter a value in the range 1 to 4. Note: If the dynamic attribute is set to True, the action is that of the DefaultStation definition in COMS.
device	You must provide a CUCI Device Name. This does not need to be a valid SYSTEM/COMS Device name.
dynamic	Indicates if the connection is to be kept by COMS. This attribute is optional. Allowed values are: • True, the connection is not kept by COMS • False, the connection is kept by COMS.
logoffdisconnect	Indicates whether the session is automatically logged off when the connection is terminated. This attribute must be set to True.

Example

```
Add Service RATLon
  closeaction = 3,
  device = ratlweb,
  logoffdisconnect = true
Enable Service RATLon
```

Note: For services, the **service name** associated with the declared service is the name of the next service in the connection path

TCPIP Port

Define a port to the TCPIP PCM to associate port attributes for the dialogs. Attributes can be assigned using the following syntax:

Runtime for ClearPath MCP Installation and Configuration

```
Add Port <port name>
  stationname = <name>,
  checkinterval = <number>,
  device = <name>,
  framing = <category>,
  maxoffer = <number>,
  maxoutput = <number>,
  service = <name>,
  socket = <number>,
  transport = <category>,
  windowsize = <number>
Enable Port <port name>
```

Attribute	Description
<port name>	Specifies a unique port name. <port name> must correspond with an identified service.
stationname	Specifies a unique station name. Refer to Using StationName.
checkinterval	Specifies the period of inactivity before keep alive packets are sent. <number> is specified in seconds, and must be in the range 0 through 1440.
device	Specifies the name of a device to be used for all subport connections that are passed to the CUCI PCM. <name> must be a previously configured device.
framing	Specifies the type of message delineation to be used. Message delineation indicates where a message starts and ends. <category> must be set to Standard.
maxoffer	Specifies the number of subports to be offered (made available for connection) at any time. <number> must be in the range 0 through 31.
maxoutput	Specifies the maximum number of bytes in an output message. For Big Buffer Ispecs, this must be set to 45300 (65000 for Big Buffer specs not using POF). <number> must be in the range 128 through 65535.
service	Specifies the name of a service to be used for inbound subport connections. This is the next service in the connection path. <name> defaults to <port name>.
socket	Specifies the socket number used by the client to connect to the port file. <number> should be set to the recommended value of 2449, unless a non-standard port configuration exists.
transport	Identifies the transport to be used. <category> must be set to TCPIP, or it defaults to null.

Attribute	Description
windowssize	Specifies the maximum number of bytes that can be queued, on input, per dialog before more is received. For Big Buffer Specs, this must be set to 45300.

Example

```
Add Port RATL
  stationname = actlinc/#,
  checkinterval = 5,
  device = ratlweb,
  framing = standard,
  maxoffer = 1,
  maxoutput = 10000,
  service = ratl,
  socket = 2449,
  transport = tcpip,
  maxoffer = 500
Enable Port RATL
```

Using StationName

This attribute names a connection to COMS. It provides a flexible format from which station names can be generated.

Note: Refer to <tcpip connection name> field of the Add or Modify TCP/IP PCM command in the ClearPath MCP Software Custom Connect Facility Administration and Programming Guide for all possible station name values.

When developing a station name, you need to consider uniqueness and determinability. For example, you might require that the station name be consistent each time a particular user connects, and will not change over time. You might also require that more than one connection be used from the same client or from any number of clients and each name used is unique.

You also need to consider any COMS security that is applied to station names and how these stations comply.

For the best means of ensuring a consistently unique name, use the <tcpip psnf> attributes \$yourhost or \$yourIPaddress within the stationname attribute value.

If a hostname is desired but an IP address is formed for the stationname instead, that is the letters **IP** are inserted in front of the address, it might be possible to use TCP/IP mapping to set the hostname. Refer to the *TCP/IP Implementation and Operations Guide* for more information on mapping IP addresses.

On some networks, such as Dynamic Host Configuration Protocol (DHCP), IP addresses are not consistent over time. In this situation there are two possible alternatives:

- Reserving a period of time where the IP address remains stable.
- Configuring a Domain Name Server (DNS) so TCP/IP can resolve an IP address to a known hostname.

Refer to the *TCP/IP Distributed System Services (DSS) Operations Guide* for more information on configuring a DNS Resolver.

Overriding the Stationname by Client

When a station name is set by the client it overrides the configured setting defined for RATL connections above. Refer to the *Agile Business Suite Component Enabler User Guide* for more information on setting the station name by client. The station name supplied by the client might have a numerator applied to uniquely qualify the name, where multiple connections are desired from the same client. The numerator is represented by a string of one or more consecutive hash characters (#) appended to the station name which is converted to a unique ascending number. The number of consecutive hash characters indicates the minimum number of digits to be appended. For example, a supplied station name of user#### results in names of the form: USER001, USER002, USER003 ... USER999, USER1000, USER1001 etc

The effect of StationName on station name (Glb.Stn)

The setting of the internal station name, or attribute Glb.Stn, is affected by the external (COMS) station name.

For Component Enabler (or NOF) based connections the value of Glb.Stn is based on the COMS station name value and the Remote Access service attribute StationNamePrefix value. If the StationNamePrefix is not defined then Glb.Stn is prefixed by the letters **RAT**, as shown in the first example below. If the derived station name is longer than the limit of 17 characters, the connection attributes for **yourhost** is used, as shown in the second example below. If the value for yourhost is not known or it is longer than the 17 character limit, the value for **youripaddress** is used. If this value is also too long the IP address is converted to its integer equivalent, as shown in the third example below.

Stationname Prefix values of NONE, None, or none have a special meaning. Refer to the table to know more about the values.

The following example shows the resulting COMS and station names for a client with the specified Port Stationname format, a station name prefix set or not set to **SNP**, a hostname of Timbertown, and an IP address of 123.132.213.231:

TCPIP Port StationName	RATL Service StationName Prefix	COMS Station Name	Glb.Stn
ACTLINC/#	<null>	ACTLINC/1	RATACTLINC/1
	SNP	SNPACTLINC/1	ACTLINC/1
	NONE/None/none	ACTLINC/1	ACTLINC/1

TCPIP Port StationName	RATL Service StationName Prefix	COMS Station Name	Glb.Stn
\$yourhost/ \$youraddress	<null>	TIMBERTOWN/1234	RATTIMBERTOWN/1
	SNP	SNPTIMBERTOWN/1234	TIMBERTOWN/1
	NONE/None/none	TIMBERTOWN/1234	TIMBERTOWN/1234
\$youripaddress/#	<null>	123_132_213_231/1	RAT2072303079/1
	SNP	SNP123_132_213_231/1	123_132_213_231/1
	NONE/None/none	123_132_213_231/1	123_132_213_231/1

RATL Configuration

Configure the following entities:

- Service
- View
- Language

RATL Configuration Syntax

You can use the following verbs in CCF to configure the server for Component Enabler, or Web Enabler:

Verb	How it is Used
Add	To define attributes for Views, Languages, Services, MQservers, MQclients, and MQrequests.
Delete	To change existing Views, Languages, Services, MQservers, MQclients, and MQrequests. The View, Language, Service, MQserver, MQclient, or MQrequest must be disabled before it can be deleted or modified.
Disable	To change existing Views, Services, and MQrequests. The View, Service, or MQrequest must be disabled before it can be deleted or modified.
Enable	To enable existing Views, Services, and MQrequests.
List	To list Dialogs, Services, Languages, Views, MQservers, MQclients, and MQrequests.
Modify	To define attributes for Views, Languages, Services, MQservers, MQclients, and MQrequests. The View, Language, Service, MQserver, MQclient, and MQrequest must be disabled before it can be deleted or modified.

Verb	How it is Used
Option	To change server program runtime options.
Show	To show existing Views, Services, Languages, connected Dialogs, MQservers, MQclients, and MQrequests.
Status	To show the status of the PCM, such as compile time, code version, and title.
Trace	To alter or show the trace options.

Service

Identify a service to the PCM to associate the connection path for dialogs. Attributes are assigned using the following syntax:

```
Add Service <service name>
  service = <name>,
  NOFidentity = <name>,
  SwitchToFireUp = <boolean>,
  StationNamePrefix = <name>
Enable Service <service name>
```

Attribute	Description
<service name>	Defines a unique service name.
service	Specifies the name of a service to which inbound stations should be connected. This is the next service in the connection path. <name> must be a previously configured service.
NOFidentity	Identifies the connection types of the applications. <name> is a COMS Security Category List configuration entity that is defined in COMS. If the attribute is not configured in the service definition, it must be defined using the SecurityCatList attribute in the CUCI service definition before the server can handle the Component Enabler connections.
SwitchToFireUp	Specifies behavior when switching back to an application from which a switch previously occurred. This attribute is optional. If True, returns to the Fireup Ispec instead of the Ispec from which the original switch occurred. If False, returns to the Ispec from which the original switch occurred. If the client has not previously been displayed, the Fireup Ispec is retrieved. Any data contained in the SwitchTo command overrides the setting of this attribute.

Attribute	Description
StationNamePrefix	Prevents the RAT station name prefix appearing in Glb.Stn for Component Enabler connections. <name> prefixes the COMS Station Name. Refer to Using StationName. This attribute is optional.
MARCOpenText	Allows input to be passed to the MARC dialog when a new COMS connection is established from the server to a desired application. The value must be enclosed in double quotation marks. When this attribute is present the text is sent instead of the server passing a hard coded message to the MDPLAUNCH window. Note: In order for the command to be carried out successfully by MARC, the CUCI Device attribute marccapable must be set to true.

Example

```
Add Service RATL
  service = LINC,
  NOFidentity = SCL_NOF,
  SwitchToFireUp = False,
  StationNamePrefix = AL/
Enable Service RATL
```

Configuring Remote Access Server Entities

The Remote Access configuration entities for the COMS Security Category List names must be configured in at least one of the following attributes of the CCF configuration:

- SecurityCatList in the CUCI service definition
- NOFidentity in the service definition

Refer to RATL Configuration Syntax for more information about the syntax used to configure the server in an MCP environment.

When configuring entities you can change their names, but the names must remain unique. You can define additional Port and Service entities ensuring that a connection path can be resolved through CCF, encompassing the PCMs from TCIP using the Remote Access server to CUCI. Refer to the *Custom Connect Facility Administration and Programming Guide* for more information on using CCF.

View

You can identify Views to the PCM to associate connection criteria for Component Enabler users to access applications. A View can refer to one or more applications, or different Views might apply to the same application.

To identify at least one application, you can assign attributes using the following syntax:

```
Add View <view name>
  application = <system>,
  level = <number>,
  window = <name>,
  usercode = <usercode>,
  language = <language>
  comsstatuscheck = <boolean>
Enable View <view name>
```

Attribute	Description
<view name>	Specifies a unique view name.
application	Indicates the name of the initial application to be accessed through this View. This attribute is optional. <system> might contain the usercode, the application name and the Dictionary name of the built application. The Dictionary contains the LINCGLI, LINCFORM, and LINCCNTL files for the built application.
ComsStatusCheck	Specifies behavior when the transaction encounters a COMS Disabled Database on the MCP server. If True, an error 202 is returned to the client immediately. If False, the transaction will timeout.
level	Indicates the command level for dialogs using this View. This attribute is optional and only applies to NOF based connections.
window	Specifies the COMS window to be used by this View. This attribute is optional, but is required when the application to which you might need to switch is not already in use.
usercode	Indicates the usercode for every dialog that is established for this View. If it is not present, the client is asked for a usercode. This attribute is optional. <usercode> must be valid for the purposes of workstations connected to Runtime through COMS.
language	Indicates the preferred language to be used for this View. This attribute is optional. <language> must be a previously identified language.

Example

```
Add View sample_auto
  application = (USER1)SAMPSYS on DICTPACK,
  level = 0,
  window = SAMPLE
  usercode = anonymous,
  language = english
Enable View sample_auto
```

Language

Identify a language to associate the ISO Country code and an ISO Language code with a language name. The ISO Language code is defined in ISO 639 while the ISO Country code is defined in ISO 3166. These standards are available in the official ISO website, <http://www.iso.ch/>.

Language names are configured in the application. Attributes can be assigned and enabled using the following syntax:

```
Add Language <language>
  ISOC = <country code>,
  ISOL = <language code>
```

Attribute	Description
ISOC	Specifies the ISO Country code to be associated with the language name.
ISOL	Specifies the ISO Language code to be associated with the language name.

Example

```
Add Language english
  ISOC = EN,
  ISOL = EN
```

Message Queuing

Message Queuing allows multiple concurrent users of Component Enabler to access an Agile Business application, by making more efficient use of system resources, and reducing the overheads associated with establishing and maintaining individual connections for each user session. This is an alternative to the existing method of connecting to the Runtime application using individual TCP/IP connections.

Refer to the *Agile Business Suite Component Enabler User Guide* for more information on how to use message queuing for Component Enabler Scalability.

The following entities are added to the PCM section of the CCF params file to configure the request queues and connection details of the FalconMQ Server and FalconMQ Client library:

- MQServer
- MQclient
- MQrequest

MQServer

```
Add MQServer <name>
  Servername = <name>,
  IPaddress = <ipaddress>,
  Port = <number>,
  Domain = <name>,
  UserName = <name>,
  Password = <name>,
```

Set attributes associated with the FalconMQ server using the following syntax:

Attribute	Description
Servername	The name of the FalconMQ server. Default: <MQserver name>
IPaddress	The IPaddress of the FalconMQ server. An assigned IPaddress overrides any specified Servername.
Port	The required port number. Default: 0
Domain	The Windows security domain. Default: nulls
UserName	The Windows user name. Default: nulls
Password	The password associated with the Windows user name. Default: nulls

Note: Case sensitive names that refer to a Windows entity can be enclosed by single quotes to prevent uppercasing.

You can also use the following commands:

- Modify attributes of existing server entities

```
modify MQServer <name>
  <attribute> = <value>,
```
- Itemize all declared MQServers

```
list MQServers
```
- Display the attributes for the selected server

```
show MQServer <name>
```

- Remove the selected server entity

```
delete MQServer <name or list>
```

Example (*italics* denote responses):

```
Add MQserver FMQS
  IPaddress = 123.1.2.3,
  Port = 1100,
  Domain = realm,
  UserName = dnote,
  Password = test,
MQserver FMQS added
Show MQserver FMQS
1 FMQS
  IPaddress = 123.1.2.3
  Port = 1100
  Domain = realm
  UserName = dnote
  Password = test
```

MQClient

Set attributes associated with the FalconMQ client using the following syntax:

```
Add MQclient <name>
  Functionname = <name>
```

Attribute	Description
Functionname	The System Library function name. Default: <MQclient name>

You can also use the following commands:

- Modify attributes of existing client entities.

```
modify MQclient <name>
  <attribute> = <value>,
```

- Itemize all declared MQclients.

```
list MQclient
```

- Display the attributes for the selected client.

```
show MQclient <name>
```

- Remove the selected client entity.

```
delete MQclient <name or list>
```

Example (*italics* denote responses):

```
Add MQclient FalconMQSupport
MQclient FALCONMQSUPPORT added
Enable MQclient FalconMQSupport
MQclient FALCONMQSUPPORT enabled
```

MQrequest

Set attributes associated with the request queue using the following syntax:

```
Add MQrequest <name>
  MQclient = <name>,
  MQserver = <name>,
  Pathname = <name>,
  Processes = <number>,
  Station Name = <SNformat>,
  Usercode = <identifier>,
  View = <name>,
  Service = <name>
```

Attribute	Description
MQclient	The name of the FalconMQclient.
MQserver	The name of the FalconMQ server.
Pathname	The request queue path name. Default: .\PRIVATES\$\<MQrequestname>
Processes	The number of queue reader processes. Default: 1
Stationname	The pooling station name format. The possible Snformats are as follows: • <literal> • / • # • \$ – – MQclient – – MQrequest – – MQserver – – ServerName – – IPaddress – – Domain – – Username Default: \$MQrequest/#
Usercode	The pooling user code.
View	The name of the view. Default: <MQrequestname>

Attribute	Description
MQrequestname>	The service name. Default: <first service name defined (in Remote Access Server)>

You can also use the following commands:

- Modify attributes of existing MQrequest entities.

```
modify MQrequest <name>  
  <attribute> = <value>,
```
- Terminate the selected MQrequest reader process.

```
disable MQclient <name>
```
- Execute the selected MQrequest reader process.

```
enable MQrequest <name>
```
- Itemize all declared MSQclients.

```
list MQrequest
```
- Display the attributes for the selected client.

```
show MQclient <name>
```
- Remove the selected MQrequest entity.

```
delete MQrequest <name or list>
```

Example (*italics* denote responses):

```
Add MQrequest sampleQ  
  MQclient = FalconMQSupport,  
  MQserver = FMQS,  
  Usercode = legion,  
  View = samplesystem,  
  Service = ratl  
MQrequest sampleQ added  
List MQrequests  
MQrequests:  
1 sampleQ
```

COMS Configuration

To define connection types to applications, you need to define two COMS configuration entities. These are Security Category List and Installation Data entities. The names used in the CCF configuration for SecurityCatList (CUCI device attribute), and NOFidentity, should correspond to the names of Security Category List entities in the COMS configuration. Each Security Category List entity needs a corresponding Installation Data entity. The value assigned to the INTEGER1 attribute determines the type of connection for that entity. Currently, the only allowable value for INTEGER1 is 9.

You can define Component Enabler (NOF) based connection types for applications using the following COMS configuration entries:

```
CREATE INSTALLATION_DATA RATL_NOF
  INTEGER1 = 9
CREATE SECURITY_CATEGORY_LIST RATL_NOF
  ID = RATL_NOF
```

Remote Access Server Commands

Clear Command

This command is used to clear connections from the PCM.

Syntax:

```
Clear Dialog<#,name, or list>
```

Example:

```
Clear Dialogs 1,4-7,9
```

Option Command

The following list outlines the options users can set:

- AllAttributes
- ShowAsserts
- AssertDump
- CompactTables
- LogicError1
- LogicError2
- ForwardSyncMessages

When set any received CCF Sync protocol messages are sent onwards, otherwise they are ignored.

Syntax:

```
Option [+/-] <option list>
```

Example:

```
Option +ForwardSyncMessages
```

- NoStationNameOverride

When set prevents clients from overriding the station name configured for RATL connections. It can only be set in the CCF configuration file and its default value is off.

Administering the Remote Access Server

Administering the Remote Access Server involves the following tasks

- Starting and stopping
- Monitoring
- Security
- Tracing

Starting and Stopping

Use the CCF commands to start and stop the server and to monitor or trace server activities.

Note: Any connections to COMS or a COMS application via NX Services (for example, NX view) are terminated.

Because the server is configured as part of CCF, starting and stopping CCF starts and stops the server:

- To start Remote Access Server along with CCF, use:
`NA CCF+`
- To stop Remote Access Server along with CCF, use:
`NA CCF-`

Alternatively, the server can be started and stopped without disrupting CCF:

- To start Remote Access Server without affecting CCF, use:
`NA CCF enable pcm ratlpcm`
- To stop Remote Access Server without affecting CCF, use:
`NA CCF disable pcm ratlpcm`

Monitoring

You can monitor the status of any Remote Access server component configured in CCF, such as Languages, Views, and Dialogs. You can use the CCF **STATUS** or **SHOW** commands to display the status of the selected component.

The following example uses the **STATUS** command to display the status of the PCM. It displays the version, timestamp, internal program options and default language.

```
NA CCF RATLPCM STATUS
```

This command returns the following data:

```
Unisys Corporation COMSock
RATLPCM 58.189.8010 (586,586) 11/18/20 21:35:52
Compile Options:Trace, Assert
Language = ENGLISH
```

The following example uses the **SHOW** command to display the status of the connected dialog.

```
NA CCF RATLPCM SHOW DIALOG 1
```

This command returns the following data:

```
Sunday 09/20/98 10:29:31
1 RATL/UNO
Client = Open
Transport = Open
Service = Open
Input Seq Num = 8
Output Seq Num = 6
NOF = True
GUI = False
View = UNO
Language = SPANISH
Device = RATLWEB
Maxoutput = 6000
HostName = ACUSAHA
ACVT = Default
```

Security

If a host application supports password aging and the Remote Access server is compliant with the application then user passwords can be changed when using the Remote Access server.

Refer to the *Security Operations Guide* for more information on setting password aging on an MCP host.

Tracing

Use CCF commands to start and stop tracing and to set the tracing attributes. Tracing can be initiated either by the operator, or by the client as part of the connection request. Tracing is normally used only for problem resolution, as it might impact the performance of the server.

The options for the CCF TRACE command are:

ON or RESUME	Turns tracing on.
OFF or SUSPEND	Turns tracing off.
CLOSE	Closes the current trace file.

You can set trace attributes to specify which activity is traced. The trace attributes are listed in the following table:

Attribute	Components Traced
RATL	RATL protocol
ALLDLGS	All dialogs
Attach	Session establishment and termination

Attribute	Components Traced
Blocked	Suspended and resumed output
CMDINFO	CCF command data buffer
CREDITS	Bytes available for transmission
DATAINFO	CCF associated data buffer
DATAPATH	Procedural flow of message buffering
FULL	Shows full size of data buffers
LISTBUFS	Internal data space processing
LOCKS	Contention
MISC	Miscellaneous
MISCPROCS	Miscellaneous processing
MQ	Message Queue interface
MSG	Message displays
OPERINP	Operational interface
PFD	Configuration file parameters
SCANNER	Parsing
TBL	Tables

An example of the CCF command to start tracing all dialogs for the Remote Access server is as follows:

```
NA CCF RATLPCM TRACE ON +ALLDLGS
```

Remote Access Server Protocol Response Messages

In particular situations the server sends protocol messages, with a number of possible response codes, to the client.

The following table outlines some of the more common codes and possible causes, to assist in determining the cause of the message:

Response Code	Meaning	Possible Causes
100	Successful operation	Session was successfully established.
101	Login is required	The View does not contain a usercode attribute setting.
102	Secure Login	The client must complete a secure login.

Runtime for ClearPath MCP Installation and Configuration

Response Code	Meaning	Possible Causes
103	Additional login	The userdata file indicates that other required user related attributes are needed.
201	Application does not exist	Either the View is not known to the server or the application referred to in the View does not exist.
202	Application cannot be started	The application is disabled.
203	Application cannot be contacted	Unable to read or obtain the desired information from the control file.
204	Access denied	• Application is not EAE 3.3 or later release. • Userdata validation error (invalid usercode/password). • Duplicate connection name. • Usercode specified on View does not exist or is not valid. • COMS Window for the Application does not exist or is not valid (window list). • Security Category List used by connection does not exist in COMS. • Failed COMS Usercode/Station name security checking.
205	Access denied, shut	Access to the application is denied and connection is closed. NGENSERVICES might not be available. Start the system from the host or set minimum copies for the Primary subsystem to a value greater than 0.
206	Unsupported	Client protocol level is not supported.
207	Application Limit	Application table full. Under normal operating conditions, this error can occur if NGENSERVICES is not available for the application.
302	Protocol error	A protocol error was detected.
401	Calls unsupported	Method calls are not supported.
402	Name unknown	Method name is unknown.
403	Parameter error	Method parameter problem.
404	Call error	Method call returned an error.
405	Call unknown error	Method call returned an unknown error.

Localization of Messages

Remote Access Server messages can be translated using the MCP-based Multilingual System (MLS). The user messages are stored in the program SYSTEM/LINC/PCM/RATL in the following arrays:

- pcm_msgs
- login_prompts
- login_labels

Configuring TLS 1.2 Remote Access Server

A TLS certificate must be installed on the server to ensure a secure connection and protect all important information. You must first create a TLS 1.2 certificate on the MCP host machine before importing the security certificate using Security Center.

Notes:

- *Earlier TLS and SSL levels are not supported due to known vulnerabilities. Only TLS 1.2 level is supported.*
- *In the following procedure, the use of the terminology SSL is restricted to the MCP file attributes and TCP/IP properties where SSL is used as a generic identifier for a secure layer.*

To configure the TLS Remote Access Server, perform the following:

1. Create the TLS certificate request on the MCP host machine:
 - a. Ensure that the Security Center must be installed on the host and a PC environment.

Refer to the *MCP Security Overview and Implementation Guide* for more information.
 - b. To open the Security Center, select **All Programs > Unisys MCP > Security Center**.
 - c. Select **MCP Cryptographic Services Manager > Trusted Keys**.
 - d. Right-click on **Other Keys**, and then select **Create Key**.
 - e. Set the Application to **CCF** and the Service name to **RATLKEY**.
 - f. Set the Usercode to ***NULL**, and key strength to at least 2048.
 - g. Select the **Create Certificate Request** check box, and then fill in the remaining fields with the appropriate details (for example, Set the Signature Algorithm to SHA256_RSA).

Refer to the *Online Help* for more information.
 - h. Click **OK**.

The **Save** dialog box is displayed.
 - i. Enter the file name, and then click **Save**.

This creates a certificate request file (.req).

Note: *It is recommended that this certificate request file must be processed by a trusted third-party Certificate Authority (CA).*

2. After the .certificate request (.req) is processed by the CA, import the resulting security certificate.
 - a. Open the **Security Center**.
 - b. Select **MCP Cryptographic Services Manager > Trusted Keys**.
 - c. Expand the key store where the key was created.
 - d. Right-click the key, and then select **Options > Install Certificate Into Set**.
 - e. In the File Browser, select the **.P7B** or **.P7C** file.

When the certificate is successfully installed a green check mark appears next to the name of the certificate.

Note: *If you are using a non-trusted CA, the created .P7B or .P7C file will be ready for installing or importing on the client. This same process must be followed if you are using a self-signed certificate.*

3. Configure the RATL TLS port:

The supplied file NGEN29/SAMPLE/CCF/PARAMS/RATL contains the necessary configurations for RATL TLS. These must be customized to suit your environment.

The added configurations are

- a. PORT RATLTLS

As per PORT RATL with the additions/change of:

SERVICE = RATLTLS,

SOCKET = 2448, % choose your socket number

SSLSECUREMODE = TRUE, % always

SSLKEYCONTAINER = CCF_RATLKEY; % the key name, this must be the concatenation of the two names used in 1 (e) above using a '_'.

- b. SERVICE RATLTLS

As per SERVICE RATL

Additionally, packet security must be enabled on TCPIP.

From MARC: NW TCPIP OPT +SSL

Refer to the *MCP Security Overview and Implementation Guide* and *TCP/IP Distributed Systems Services Operations Guide* for more information on MCP security.

See "Windows TLS Certificate Installation" for more information on installing the TLS certificate on Windows.

Installing and Configuring Remote Subroutine Server

The Remote Subroutine Server (also known as LRSS) enables Debugger to call subroutines from host Runtime platforms.

There are two methods of installing Remote Subroutine Server:

- You can install it as part of the standard installation of Runtime software (refer to [Installing the MCP Runtime Software](#)).
- You can install it independently using the LRSS install WFL.

Independent Installation

To install the Remote Subroutine Server, enter the following command:

```
START NGEN29/SAMPLE/LRSS/INSTALL ("usercode", "packname")
```

The location of the files is based on the current directory. A Usercode and Pack name might be provided as optional parameters to the install job.

The install job performs the following:

- Registers the Remote Subroutine Server as a Distributed System Services (DSS) provider
- Maps the Support Library (SL) function names for Remote Subroutine Server

Alternatively, the installation can be performed manually. Use the following commands from the system console or a suitably privileged station:

1. To register Remote Subroutine Server as a DSS provider enter the following command:

```
NA LOAD COMMANDS LRSS/DSS/REGISTER
```

2. To map Support Library (SL) function names for Remote Subroutine Server enter the following command:

```
SL LRSSSUPPORT= SYSTEM/LRSS/SUPPORT: TRUSTED, LINKCLASS= 1  
SL LRSSPDUSUPPORT= SYSTEM/LRSS/PDUSUPPORT: TRUSTED, LINKCLASS= 3
```

Note: Usercode and Pack names might need to be inserted into the above commands as applicable.

Configuration

To configure Remote Subroutine Server you need to set the options in the configuration file that is read at startup. The file is at LRSS/CONFIG and all options have default settings, so users only need to change them if the need arises.

The options are:

```
PORT = <Integer, 0 to 65535, default 6004>
```

```
CONNECTIONS =          <Integer, 1 to 4000, default 12>
MAXOFFER =             <Integer, 1 to 99, default 1>
INACTIVITY =           <Integer, 1 to 1440, default 10 minutes>
TIMEOUT =              <Integer, 1 to 1440, default 60 minutes>
ERRORS =               <File name, default LRSS/ERRORS>
TRACE =                {ON | OFF (default) [[TO] <File name, default LRSS/
                        TRACE/#>]}
```

These options are:

- **PORT**

The Port is the TCP/IP communications service number used to establish incoming connections from prospective clients.

- **CONNECTIONS**

Connections is used to limit the total number of concurrent sessions available.

- **MAXOFFER**

MaxOffer controls the number of listening port subfiles that are available. The range is either 1 through 99, or 1 through the number of connections allowed (if less than 99).

- **INACTIVITY**

Inactivity is the interval of time between when TCP/IP keep alive packets are exchanged with the client. The inactivity value is mapped to the port file attribute DialogCheckInterval.

- **TIMEOUT**

Timeout is the duration for which TCP/IP keep alive packets can continue to be sent before a connection is closed. The range is as applicable for the port file attribute BlockedTimeout.

- **ERRORS**

The Errors option locates the filename for any configuration problems found. Messages are logged to the error file with a reference to the problem line in the configuration file.

- **TRACE**

Trace is available for observing Remote Subroutine Server behavior or diagnosing problems. Tracing can be turned on or off, and the title of the trace file can also be set. The default value is off and the default title is LRSS/TRACE/#, where # is a numerator starting at zero. Each time the server starts, the trace file name's numerator restarts at zero.

- **Comments**

Comments can be placed anywhere in the text stream and are terminated by the end of each line. A comment is denoted by the presence of either a percent or an asterisk character in the text stream except when enclosed by quotation marks.

The syntax is as follows:

```
% this is a comment* and so is this
```

Operations

Remote Subroutine Server can be controlled through the Network Application (NA) interface. You can start, stop, show status or change trace options. These commands are:

Action	Command
Start	NA LRSS +
Stop	NA LRSS -
Show Status	NA LRSS STATUS
Trace	NA LRSS TRACE [ON OFF Release]

When the Release option is used on the trace command, the existing trace file is closed and a new trace file is opened with an increment to the numerator portion of the trace file title.

If Remote Subroutine Server is not running, it starts automatically when an incoming connection is attempted on the port service number registered through DSS for Remote Subroutine Server.

Monitoring

A facility exists in Remote Subroutine Server to monitor remote method calls made from its clients. The monitor facility is programmatically interfaced and provision is given to veto any remote procedure calls at hand.

Monitoring depends on the entry point within a user written application. For the monitor to work a Support Library (SL) named LRSSMONITOR must exist. This SL is checked for at startup.

The entry point is described, and an example given, in the sample source file **LRSS/MONITOR**.

Setting up FTP

Set up FTP to allow access to the usercode from Builder. Use the following SYSTEM/MAKEUSER +RU commands:

```
+RU *ANYUSER OF *IPADDRESS nnn[.nnn[.nnn[.nnn]]]  
+RU usercode OF *IPADDRESS nnn[.nnn[.nnn[.nnn]]]
```

Where nnn[.nnn[.nnn[.nnn]]] contains the required IP address nodes.

Perform the following to use Secure FTP (TLS 1.2) file transfer from the PC to the MCP host:

1. Create the TLS certificate request on the MCP host machine:
 - a. Ensure that the Security Center is installed on the host and in a PC environment.
Refer to the *MCP Security Overview and Implementation Guide* for more information.
 - b. To open the Security Center, select **All Programs > Unisys MCP > Security Center**.
 - c. Select **MCP Cryptographic Services Manager > Trusted Keys**.
 - d. Right-click on **WebTS Keys** and then select **Create Key**.
 - e. Set the Service name to **FTPTLS**.
 - f. Set the Usercode to ***NULL**, and key strength to at least 2048.
 - g. Select the **Create Certificate Request** check box, and then fill in the remaining fields with the appropriate details (for example, Set the Signature Algorithm to SHA256_RSA).
Refer to the *Developer Online Help* for more information.
 - h. Click **OK**.
The Save dialog box is displayed.
 - i. Enter the file name and then click **Save**.
This creates a certificate request file (.req).
Note: *It is recommended that this certificate request file be processed by a trusted third-party Certificate Authority (CA).*
2. After the .certificate request (.req) has been processed by the CA, import the resulting security certificate
 - a. Open the **Security Center**.
 - b. Select **MCP Cryptographic Services Manager > Trusted Keys**.
Expand the key store to where your key was created (WebTS Keys).
 - c. Right-click on your key, and then select **Options > Install Certificate Into Set**.
 - d. In the File Browser, select the appropriate .P7B or .P7C file.
When the certificate has been successfully, a green check mark appears next to the name of the certificate.
Note: *If you are using a non-trusted CA, the newly created .P7B or .P7C file is now ready for installing or importing on the client. The same process must be followed if you are using a self-signed certificate.*
3. From MARC, enable SSL on TCPIP: NW TCPIP OPT + SSL % to ensure SSL lib is active.
4. Configure the FTP properties in the FTP configuration file —
*SYSTEM/FTP/SUPPORT/CONFIGURATION

- a. Apply these changes to the FTP configuration file:
 - (1) AUTHMODE = SSL
 - (2) SSLMODE = IMPLICIT
 - (3) SSL_SERVICENAME = "FTPTLS" %your WebTS Key name from above
 - (4) INITIATE_SSL_SERVER = 1
 - (5) CLIENT_CERTIFICATES = NONE
- b. Save the updated FTP configuration file.
- c. Restart FTP
From MARC,
NA FTP – followed by
NA FTP +

Refer to the *MCP Security Overview and Implementation Guide* and *TCP/IP Distributed Systems Services Operations Guide* for more information on MCP security.

Refer to [Installing Windows TLS Certificate](#) for instructions on importing the FTP certificate into the Windows Trusted store.

Deploying the First Application After Installing Runtime

The instructions in this topic are applicable to the first deployment of your application after installing the Runtime for the first time.

Caution

After installing the Runtime, disable your application system for the duration of the deployment phase of the build to avoid duplicate LINC SUPPORT libraries from appearing during the hotswap phase of the system deployment and to activate new code files.

The below instructions describe the process of disabling the system during deployment with minimum downtime. It is important for you to read the instructions carefully.

The Delay Compile and Deploy option on the Host Login dialog box is used in conjunction with a system built with the Rebuild option to minimize the system downtime. For those who do not want to use the Delay Compile and Deploy option, refer to [Deploying the System without Delaying the Deployment](#).

It is essential that each step be performed to avoid problems during this deployment or problems in the system after the deployment.

Deploying the System with Minimal Downtime

This method of deployment results in the system being down for a minimal time. The Delay Compile and Deploy option is used to suspend the deployment, after the generate phase is complete, to provide an opportunity to disable the system. The deployment is suspended at the point of deployment or at the point of installation.

To deploy your system with a delayed deployment, perform the following:

1. As part of pre-build preparation, remove your BuilderCache and BuilderOutput directories.
2. (Optional) Add your system and critical reports to the APPL_BLD server. Use the DELAYINSTALL APPL_BLD command to cause the deployment to wait at the point where the installation (Generate WFL) starts if the Delay Compile and Deploy option is used. Skip this step if you prefer the deployment to be suspended at the point of initiating the Compile phase.

- a. Add System to APPL_BLD Server. Enter this command from the MARC Action field.

```
NA APPL_BLD_<ident> ADDSYS  NAME=<system name>
USER=<usercode> PACK=<pack>
```

Where <ident> is the identity of APPL_BLD.

Refer to the ADDSYS command in the *Agile Business Suite Runtime for ClearPath MCP Administration Guide*.

- b. Get the index number for the system. Enter this command from the MARC Action field.

```
NA APPL_BLD_90 INDEX
```

- c. Note the index number for the system from the results of the inquiry in Step b.
 - d. Add Critical reports to the APPL_BLD Server. Enter one of the following commands from the MARC Action field.

```
NA APPL_BLD_<ident> ADDREP  <nn> =
<report name>[, <report name2> . .]
NA APPL_BLD_<ident> ADDREP  <nn> #<file title>
```

Where:

<ident> is the identity of APPL_BLD.

<nn> is the system index noted in Step b.

<report name> and <report name2> are the names of reports.

<file title> is the name of a file that contains a list of reports.

Refer to the ADDREP command in the *Agile Business Suite Runtime for ClearPath MCP Administration Guide*.

- e. Set DELAYINSTALL option for the system in the APPL_BLD Server. Enter this command from the MARC Action field.

```
NA APPL_BLD_<ident> DELAYINSTALL  <nn>
```

Where <ident> is the identity of APPL_BLD, and <nn> is the system index that you noted in Step b.

Refer to the DELAYINSTALL command in the *Agile Business Suite Runtime for ClearPath MCP Administration Guide*.

3. Start the deployment.
 - a. Right-click the deployment folder and select **Rebuild** or **Folder Only Rebuild**.
 - b. On the **Host Login** dialog box, enter the login details.
 - c. Select the **Delay Compile and Deploy** option.
 - d. Change the Deploy Date and the Deploy Time to a suitable date and time in the future.

Allow sufficient time for the Build phase to complete and for you to disable the system. Include additional time if you perform Step 2. It is recommended to change the Deploy Date and Deploy Time to a day after the expected completion of the Generate phase.

- e. Click **OK**.
4. Verify that the generate phase on the client is complete and the deployment of the system is queued on the MCP server.

The Generate phase on the client is finished when the following message appears in the log.

```
The System Generate has been delayed until a later time
```

Systems queued for deployment can be viewed from the APPL_BLD server using the following command.

```
NA APPL_BLD_<ident> QUEUE
```

Where <ident> is the identity of APPL_BLD.

For default installations of APPL_BLD, <ident> is 90. For example, APPL_BLD_90.

The message returned by the QUEUE command is a list of queued systems.

```
1. 17:30:00 on 17/02/2023, Scheduled,  
System MYUSER, MYSAMPLE, MYPACK
```

Take note of the queue number for the system. It will be used in Step 6 to resume the deployment. The queue number for the example system above is 1.

Note: If you do not see the queue number and you performed Step 2, there will be a waiting entry about the delayed installation and the installation will be in the job queue.

5. Disable the system.
6. Resume the queued deployment.
 - a. If you did not perform Step 2 and found a queued generate, then perform the following steps:

From MARC, enter the command.

```
NA APPL_BLD_<ident> FORCEQ <n>
```

Where <ident> is the identity of APPL_BLD.

For the default installation of APPL_BLD, <ident> is 90. For example, APPL_BLD_90.

<n> is the number assigned to the queued deployment.

Use the number you obtained from Step 3.

For example, from MARC enter:

```
NA APPL_BLD_90 FORCEQ 1
```

The message returned from this command is as shown below.

```
Queue entry #1 set to now
```

- b. If you performed Step 2 and did not find a queued generate, perform the following:

Use the information in the waiting entry to find the job for the installation (Generate WFL) in the queue and force the job from the queue.

```
<mix> FS
```

7. If you use non-default MAXWAIT values, reapply them after the system has been deployed.

The default MAXWAIT settings are as follows.

```
COMS_LINC_TP          30 seconds
```

```
LSS                   10 seconds
```

8. Deploy system critical reports with the REBUILD option.
9. Enable the system.
10. Deploy remaining reports with the REBUILD option.

Deploying the System without Delaying the Deployment

If you do not want to use the Delay Compile and Deploy option to suspend the deployment, you can disable your system before starting the build. To build your system without delaying the deployment, perform the following steps:

1. As a pre-build preparation, remove your BuilderCache and BuilderOutput directories.
2. Disable the system.
3. Right-click the deployment folder and select **Rebuild** or **Folder Only Rebuild**.
4. On the **Host Login** dialog box, enter the login details.
5. Click **OK**.
6. On completion of the deployment, reapply MAXWAIT values.
7. Build system critical reports with the REBUILD option.
8. Enable the system.
9. Build remaining reports with the REBUILD option.

Updating the System with MCP Runtime Transfer

To update the system with MCP runtime transfer:

1. Build the source or base system using one of the sets of instructions described above. Refer to [Deploying the System with Minimal Downtime](#) or [Deploying the System without Delaying the Deployment](#) for more information.

2. Build the Runtime Transfer Utility (RTU) file with the **Rebuild** option.

Note: *You might want to perform this step as part of Step 1. Ensure that the Runtime Transfer properties are set up correctly before you Rebuild the Source System.*

3. Perform the following mandatory steps for transfers using Hands Free Configure or Compile Free Configure.
 - If you are using Hands Free Configure, the compile phase starts automatically. As such, it is necessary to disable the Target System.
 - If you are using Compile Free Configure, the system libraries are compiled during the transfer phase. As such, it is necessary to disable the system.
 - a. Disable Target System. (For an RDB system, disable the Primary System.)
 - b. For RDB Systems, check the status of the RDBSUPPORT library for the Primary System and secondary database. If it is not leaving the mix, check whether it is still linked to NGEN30/1/LIBRARY (function name NGEN30SERVICES). If it is still linked to RDBSUPPORT through NGEN30/1/LIBRARY, delink it by using the DELINK RDBSUPPORT command for NGEN30/1/LIBRARY (use the mix number for the control library).

Note: *For the transfers that are not using Hands Free Configure or Compile Free Configure, the above steps are optional.*

4. Initiate RTU by entering the command:

```
R $(<runtime usercode>)NGEN30/RTU ON <runtime pack>;
```

5. In the Transfer Startup screen, enter the <<segment>> class and configuration sets associated with the transfer.

6. In the Transfer Selection screen:

- a. Enter Y in the Tfr/Configure All Ispec Code field.

- b. In the Auto initiate configure program field:

Enter N in the Auto initiate configure program field if the Target System is not disabled at this point. Do this regardless of whether you use BNA as the transfer medium or not. It is necessary to disable the target system before you deploy it. It will be easier to do this if the Configure phase is not started automatically.

Enter Y in the Auto initiate configure program field if the Target System is disabled at this point. You will be using BNA as the transfer medium and use Hands Free Configure. If the Target System is still enabled but you want to use Hands Free Configure, perform the tasks in Step 3 to disable the Target System.

- c. Change the rest of the options on this screen as you would for a normal transfer at your site. The transfer should include the reports.

7. In the Transfer Creation screen:
 - a. Enter Y in the Auto initiate of transfer job field. The transfer phase will be initiated by RTU.
 - b. Change the other options on this screen as you would do for a normal transfer at your site.
8. If the Selected Transfer screen appears, set up the options so that both the system and reports are transferred.
9. Transmit the final screen in RTU. The Transfer phase starts after you transmit the final screen in RTU. Wait until this phase is complete and the transfer files have been transferred to the transfer medium.
10. For the transfers that do not use Hands Free Configure or Compile Free Configure, if the Target System (or Primary System) is not disabled already, it must be disabled now.
 - a. Disable the Target System. (For an RDB system, disable the Primary System.)
 - b. For RDB systems, check the status of the RDBSUPPORT library for the Primary System and secondary database. If it is not leaving the mix, check whether it is still linked to NGEN30/1/LIBRARY (function name NGEN30SERVICES). If it is still linked to DBSUPPORT through NGEN30/1/LIBRARY, delink it by using the DELINK RDBSUPPORT command for NGEN30/1/LIBRARY (use the mix number for the control library).
11. Run the Configure Utility for the transfers not using Hands Free Configure.

```
RUN $RUNTIMETRANSFER/<source config>/  
<target config>/CONFIGURE
```

(for an automated configure using a configure configuration set)
OR

```
RUN $RUNTIMETRANSFER/<source config>/CONFIGURE
```

(for a manual configure using the Configure Utility screens)
The Configure Utility will initiate the configure phase for transfers that do not use Hands Free Configure.
12. Wait for the configure phase to complete, and then enable the system.
13. For RDB systems, if there is a Standby System in the RDB system, transfer the Primary System to the Standby System.

If the RDB system does not have a Standby System, but reports are run against the secondary database, transfer reports from the Primary System to the secondary database.

Migrating to Release 8.0

Migration Procedure

Agile Business Suite Release 8.0 does not include Host Builder. If you are still using Host Builder in releases prior to 3.3, you must first migrate your application to Developer, following the instructions in the *EAE to Agile Business Suite Migration Guide*.

You must then migrate your application from 3.3 to Agile Business Suite 8.0 following the instructions in the *EAE 3.3 to Agile Business Suite Migration Guide*.

Notes:

- *Change in naming convention – In previous products, the naming convention for the first node in the directories for the runtime software has been LINCxx and LINCxxSYS. For example, LINC17/LSS, LINC17/1/LINCSUPPORT, LINC17/WFL/GENERATE, LINC17SYS/BLD, etc. The naming convention for these directory nodes is now NGENxx and NGENxxSYS. For example, NGEN29/LSS, NGEN29/1/LINCSUPPORT, NGEN29/WFL/GENERATE, NGEN29SYS/BLD, etc. If you have jobs or non-EAE applications that refer to any of these files, you must change the first directory node from LINC17[SYS] to NGEN29[SYS].*

The naming convention for two SLs has also changed. LINCxxSERVICES is now NGENxxSERVICES. For this release it is NGEN29SERVICES. LINCxxMLSSUPPORT is now NGENxxMLSSUPPORT. For this release it is NGEN29MLSSUPPORT.

- *User GLI programs – If your existing user GLI programs are sending data to specs that have the system MAINT field present (standard spec or a memo spec with an automaint profile) then you must change the field name MAINT to USERMAINT.*
- *For applications that use the Remote Access Server and are being migrated from EAE, it is necessary to disable and enable CCF after the application has been deployed from AB Suite. This ensures that the RATL view for the application reads the new LINCCNTL file.*

Using Dell Storage Replication Capabilities

Dell Storage systems come with replication capabilities that allow you to make a remote copy of an application for disaster recovery backup purposes.

The following issues should be considered when using the Dell storage replication capabilities with systems:

- Capabilities within MCP based software in order to optimize data recovery
- Minimize system downtime in the event a switch to the remote system becomes necessary
- Replicating the entire disk subsystem or replicating just the application disks.

If you decide to replicate just your application disks (excluding the system disks) the steps described in Planned Recovery and Online Application Takeover are essential. (Replicating the entire disk subsystem simplifies recovery, the steps described in Planned Recovery and Online Application are not required.)

Planned Recovery

Planned recovery indicates that the application has been successfully taken to EOJ the source host.

The following table shows the non DMSII files that require mirroring:

File	Family
Lincctl	Dictpack
Linclog	Logpack
Unique/Save	Dictpack
Extract files	Extractpack
Roc Data Files	Rocpack

There are a number of files that must be synchronized between hosts, based on the assumption that the alternate family (DISK) or the backup family (PACK) is not mirrored across hosts.

These files and disk families are shown in the following table.

File	Family
*Coms/Cfile	Disk
*Coms/Cfile	Disk
*Linc/Stn/Alias	Disk

In addition, the development or runtime environments must also be present on both hosts. Having this software loaded ensures the system-wide runtime libraries are always available.

Online Application Takeover

Planned Takeover

In the case of a planned takeover, before you attempt to log into the application on the secondary host, perform the following:

1. Ensure that the latest *system/COMS/CONFIG/FULL* file details are contained in the **COMS/CFILE*.

If you are unsure, load this file (located on the dictionary pack) via the COMS batch load facility on the Utility window.

2. If the system has COMS Protected Output and Protected Input enabled, as a precaution, you can disable COMS recovery. To do this:
 - Go to the DRC window of the COMS Utility.
 - Set Create New file to Y.
 - Set RDS pointer to end to Y.
3. Log into the application. The normal application startup should proceed.

During the takeover, if you log back into the application with a different terminal id, then a new Glb-Dialoginfo record is created. If this occurs, you might want to maintain the same Installation Data across the Configuration files on both hosts. This ensures that when a user logs in to either host, the same privileges are granted by both hosts.

Unplanned Takeover

In the case of an unplanned takeover, before you attempt to log into to the application window on the secondary host, perform the following:

1. Ensure the latest *system/COMS/CONFIG/FULL* file details are contained in the **COMS/CFILE*.

If you are unsure, load this file (located on the dictionary pack) via the COMS batch load facility on the Utility window.
2. If the application has COMS Protected Output and Protected Input enabled, as a precaution, you can disable COMS recovery. To do this:
 - Go to the DRC window of the COMS Utility.
 - Set Create New file to Y.
 - Set RDS pointer to end to Y.
3. Log into the application. At this stage **SYSTEM/DMRECOVERY* is started to recover the database. If there are any DMSII recovery issues, refer to your DMSII Utilities manual.

Notes:

- *Once DMRECOVERY is complete, LSS restarts any Reports that were running at the time of the takeover. Refer to Report Recovery During Unplanned Takeover for more information on this phase of recovery.*
- *The application attribute Glb.Unique value is increased by 2,500 from the value contained on the source host before the takeover.*
- *The LINCLOG will have lost a number of records, depending upon when the log buffer was last flushed. If the LINCLOG is critical to your application, it might be necessary to implement procedures where the LINCLOG is regularly released to minimize the impact of losing any records.*

During the takeover, if a user logs back in to the application with a different terminal id, a new Glb-Dialoginfo record is created. If this is the case, it would be good practice to ensure the same Installation Data is maintained across both hosts' Configuration files. This ensures that when the user logs on to either host, the same privileges are granted.

If the user logs back with a different terminal id, the last screen might not be able to be recalled, and the following error is displayed:

```
MESSAGE NOT AVAILABLE FOR RECALL; ERROR
```

This also indicates that the last instance of Glb.Work is no longer available.

Unplanned Takeover during Reorganization or Application Build

If an unplanned takeover occurs during a reorganization or an application build, it is necessary to:

- Reload the application from the latest backups.
- Start the reorganization or build from the beginning.

Report Recovery During Unplanned Takeover

Reports are restarted by LSS when the SYSTEM/DMRECOVERY completes on the secondary application.

In the following two cases, the Reports were all restarted with Critical Points. If any Reports that do not contain Critical Points are restarted, then those Reports are run from the beginning. Consequently, all Report output is started from the beginning.

Reports Creating Extract Files

The Report restarts from the last Critical Point, and if the Extract pack is mirrored, the Extract file continues writing records from the last record written at the Critical Point.

Reports Using ROC Flat Files

The Report restarts from the last Critical Point, and if the ROC data pack is mirrored, the Report continues writing records from the last record written at the Critical Point.

You should take care when the Report completes, or the Report is released for printing, because the ROC sleeping Report attempts to route the Report back to the source host for printing. At this stage, the source host might not be available.

It might be necessary to set ROC to 0, and when the Report completes, send it to a new destination using the ROC Inquiry screens. This only applies to restarted Reports.

Reports Writing Directly to a Printer Backup

The Report restarts from the last Critical Point. It is unlikely that the backup family is mirrored, in which case the Report output completed at the last Critical Point is on the backup family of the primary host, which might not now be available. All new output from this restarted Report is written to the backup family on the secondary host.

Configuring a Secure Client to APPL BLD Connection

A TLS certificate must be installed on the server to ensure a secure connection and to protect all the important information. You must first create a TLS certificate on the MCP host machine before importing the security certificate using Security Center.

Notes:

- *Earlier levels of TLS and SSL are not supported due to known vulnerabilities. Only TLS 1.2 level is supported. It is recommended to enable only TLS 1.2 on the MCP Hosts when using an encrypted Remote Access Server connection to access an AB Suite MCP application.*
- *In the following procedure, the use of terminology SSL is restricted to the MCP file attributes and TCP/IP properties, where, SSL is used as a generic identifier for a secure layer.*

To configure the TLS Remote Access Server, perform the following:

1. Create the TLS certificate request on the MCP host machine:

Note: *Ensure that the Security Center is installed on the host and PC environment. Refer to the MCP Security Overview and Implementation Guide for more information.*

- a. To open the Security Center, select **All Programs > Unisys MCP > Security Center**.
- b. Select **MCP Cryptographic Services Manager > Trusted Keys**.
- c. Right-click **Other Keys**, and select **Create Key**.
- d. Set the Application to **ABSUITE** and the Service name to **APPLBLD**.
- e. Set the Usercode to ***NULL**, and key strength to at least 2048.
- f. Select the **Create Certificate Request** check box, and then fill in the remaining fields with the appropriate details (for example, Set the Signature Algorithm to SHA256_RSA).
- g. Click **OK**.
The **Save** dialog box appears.
- h. Enter the file name and click **Save**.

This creates a certificate request file (.req).

Note: *It is recommended that this certificate request file must be processed by a trusted third-party Certificate Authority (CA).*

2. After the .certificate request (.req) is processed by the CA, import the resulting security certificate:
 - a. Open the Security Center.
 - b. Select **MCP Cryptographic Services Manager > Trusted Keys**. Expand the key store to locate where the key is created.
 - c. Right-click on your key, and then select **Options > Install Certificate Into Set**.
 - d. In the File Browser, select the **.P7B** or **.P7C** file.

When the certificate is successfully installed a green check mark appears next to the name of the certificate.

Note: *If you are using a non-trusted CA, the created .P7B or .P7C file will be ready for installing or importing on the client. You have to follow the same process if you are using a self-signed certificate.*

3. Configure the **APPL BLD TLS** port:

To configure the APPL BLD TLS port, ensure that the comment symbol % is removed from the TLSKEY parameter in the NGEN29/APPL_BLD_<id>/INI file. For example,

```
...
%trace_tree
TLSKEY = ABSUITE_APPLBLD
```

Note: *<id> is the APPL_BLD identifier. Using the default APPL_BLD identifier 80, the name of the INI file is NGEN29/APPL_BLD_80/INI. If you have installed a custom Appl Bld, with the identifier 80A, the name of the INI file will be NGEN29/APPL_BLD_80A/INI.*

If NGEN29/APPL_BLD_<id>/INI does not exist under the Runtime usercode, you will be prompted to reply if you want to install it during the next Runtime installation.

The Appl Bld must be restarted after the updated ./INI file is saved. The setting can be confirmed by scrolling through the response for an Appl Bld SUMM command. Additionally, packet security must be enabled on the TCP/IP.

Additionally, packet security must be enabled on the TCP/IP.

```
From MARC: NW TCPIP OPT +SSL
```

Refer to the *MCP Security Overview and Implementation Guide* and *TCP/IP Distributed Systems Services Operations Guide* for more information on MCP security.

See “Windows TLS Certificate Installation” for more information on installing the TLS certificate on Windows.

Section 9

Runtime for ClearPath OS 2200 Installation and Configuration

This section describes the installation of Agile Business Suite Runtime for ClearPath OS 2200 Operating System.

Notations

Italics is used to refer to variables, such as *system*. Enter an actual value in place of these, as instructed. Square brackets are used to refer to optional values.

In this section, an HVTIP-imposed limit of 262K words is specified and this refers to UCS.

Pre-installation Requirements

This section describes the tasks that you must perform before you install the Agile Business Suite Runtime for OS 2200.

About Agile Business Suite Software

Agile Business Suite software is supplied on a release tape. This tape contains the Runtime and Report Output Control (ROC) system.

Throughout this document, release tape is used as a general term.

The AB Suite base system software comprises the following products:

- Runtime (mandatory)
Runtime is the basic product that enables all the other Agile Business Suite software to run. Therefore, Runtime must be the first product you install. See [Installing AB Suite Runtime for ClearPath OS 2200](#) to view the list of files available on this tape.
- Report Output Control (ROC) System
ROC is a system that controls the output from Reports. It enables you to browse a Report output online, schedule printing, and print to terminal or site printers.
ROC must be installed after Runtime. There can be multiple ROC systems in a Runtime.

Hardware Requirements

This section describes the recommended hardware requirements for running the Agile Business Suite Runtime for OS 2200. The size estimates are exclusive of any other existing software.

Requirement	Details
Host	CP-OS2200-19.0 or CP-OS2200-19.0 on Dorado and SAIL-based systems. CP-OS2200-19.0 or CP-OS2200-19.0 on ClearPath OS 2200 Software Series.
Memory	Nine to eleven million words of memory with three to four million words reserved for the TIP memory. Notes: • <i>The TIP memory is dynamic and does not require configuration.</i> • <i>These memory requirements restricts other external systems or other development activities.</i>
Disk storage	Minimum of 3,000 tracks. Minimum of 10,000 tracks, if you are using ROC.
Terminals	Following table lists the supported terminals.
Other peripherals	Line printer and tape drive.

Terminals Supported

This release supports the following terminal types:

UTS 20	UTS 20L	UTS 20R
UTS 30	UTS 40	UTS 60
UTS 60I	SVT 1120	SVT 1121
LT300	DS7	IBM 3270 group of terminals
SNA3270 logical terminals	PCs with UTS terminal emulation software	

Note: Agile Business Suite supports the LT300 terminal operating in SVT1121-compatible mode. The LT300 is an internationalized terminal with multiple character set capabilities that supports many of the ISO 8859 8-bit character sets.

The LT300 terminal type is recognized by the :STN colon command and is a valid value for the Glb.Style built-in segment attribute.

The CMS and MCB recognize the LT300 as a supported terminal type and identify the Coded Character Set (CCS) for each message from LT300. The CCS is a one-to-one mapping of characters in a character set to their internal binary representation. Agile Business Suite stores the CCS identifier (CCS ID) for the input message in the GLB.CCS built-in segment attribute.

System Software Requirements

This section describes the mandatory and optional OS 2200 based system software, release CP OS 2200 18.0 or later. You should install this software as your first pre-installation task. See [Installing and Configuring the Required OS 2200 System Software](#) for details on system software installation.

Mandatory System Software

Following is a list of mandatory system software:

- EXEC

Agile Business Suite supports MHTIP and PAEXEC shared or partitioned applications (and local applications).

- TIP Utilities
- CPCOMM
- UDS control (UDSC)
- UREP and RDMS

An OS 2200 based system requires only the UREP and RDMS sub products. These are provided under UDS, but also operate with the full UREP and RDMS products. (Due to the use of FastPath, the RDMS STATISTICS option is not supported.)

- IRU
- MCB
- SOLAR
- ACOB

- You must install the full ACOB Compiler and the C\$DML ACOB Common Bank.
- The ACOB compiler must be installed as non-flagging.
- The Field data DML Common Banked library must not be used.

If you require the Field data DML Common Banked library for existing external systems, you must install a second, alternative ACOB Compiler. Refer to the *ASCII COBOL Installation Guide* for information on installing alternative Compilers.

Caution

Unless the ASCII COBOL compiler has been licensed, no other use for this compiler is authorized. In this context, other use includes compilation or execution of user-written externally generated programs.

- UCOB
- MAP
- PCIOS
- SORT
- LINK
- LSS
- URTS
- Extended Language Message System (ELMS)
- General Syntax Analyzer (GSA)
- COMUS

Optional System Software

The following table lists the optional system software and the corresponding reason for installing the software:

System Software	Details
Business Information Server	Install if you use a Business Information Server interface. You will also have to install the MRI for Business Information Server access to OS 2200 databases <i>and/or</i> IPFSQL.
MRI	Install if you use a Business Information Server interface.
IPFSQL	Install if you use an NOF interface.
DDP-PPC	Install if you use HUB. DDP-PPC is an optional product used with external and interhost Automatic Entries that use the HUB mechanism. See Other Software Considerations for more information.
PADS	Install if you use UCS applications (recommended).
OLTP-TM2200	Install if you use OLTP.

System Software	Details
OLTP-2PC	Install if you use OLTP 2PC.
OSI-TP	Install if you use OLTP multi-host capability.
UC	Install if you use OLTP UCS server systems.
Relational Database Fast Load	Install if you use the offline utility for database reorganization or Fast Load Reports.

Requirements for the Runtime Configuration Process

When you start to configure the Runtime, you have to supply replies to requests made by the configuration process for which you require the following:

- Release tape
- COMUS database
You have to create a COMUS database if you are making changes to the default configuration.
- Configuration parameters

You can accept most of the default parameters for the configuration, especially if it is a new site. However, if you have established naming conventions for jobs, files, and numbering systems for your BDIs, you have to change the parameters.

See [COMUS Configuration and SOLAR Installation Parameters](#) for information on the complete parameter set and for detailed information about the configuration process.

Requirements for Runtime

To enable the use of commands to control the Background Run and HUB Background Run, the user ID for each background run must have SSCONSOLE privilege.

You must have an HVTIP library to hold your Runtime. This can be a single library or a shared library.

Requirements for ROC

To install ROC, you require the following:

- Installed Runtime
- Runtime tape
- Names used in the Runtime configuration, such as
 - System name for the ROC system
 - Database name for the ROC system
- VALTAB entry for ROC containing the following information:

- ROC Spooler transaction ID
- TIP transaction number
- Application group number
- QPRIORITY node with a QMAX of zero for the ROC Spooler transaction ID

You might want to use Freespace files for ROC output that can give performance benefits in a high-volume printing environment. This involves an Exec configuration parameter to create a TIP Freespace control file (FS\$SYS) for ROC and to use a TEMP\$SGS parameter for ROC.

See [Configuring and Regenerating EXEC](#) for more information.

Other Software Considerations

This section describes the other software considerations that must be considered before installing the Runtime for OS 2200.

Considerations for Intersystem Communications

The external Automatic Entry (HUB) facility provides an easy-to-use method for communication between systems that can be on the same host or on different hosts.

The following table describes the software requirements for HUBs depending on the facilities that you want to use:

Facility Used	Active HUB Background Run	HUB\$SGS Element with LOCALHOST and Remote Host SGSs	Configured HUB for Runtime
No external Automatic Entries and no ROC	No	No	Yes
ROC	Yes	No	Yes
External Automatic Entries in same Runtime	Yes	No	Yes
External Automatic Entries on same host	Yes	No	Yes
Interhost external Automatic Entries	Yes	Yes	Yes

Note: ROC uses external Automatic Entries to communicate header information.

See [Installation Modes for Setting Up the HUBs](#) for more information on the installation.

Considerations when Using the UCS Subsystems

If you have a very large Ispec transaction in your system, you might want to consider setting up your system as a UCS subsystem. The mechanism involves setting parameters.

However, at the installation stage of Runtime, you have to consider user privileges, because the Runtime must be installed under a USER-ID with security attributes that allow the loading of the UCS subsystems.

Note: *The UCS Subsystems are supported only on M Series hosts with memory paging facilities.*

Considerations when Using the OLTP

Systems could use the Open or OLTP software for the external Automatic Entry facility, providing distributed transaction processing across different types of machines and networks.

Installing and Configuring the Required OS 2200 System Software

Visit the Unisys Product Support website at www.support.unisys.com for the latest information on installing and configuring the required system software.

The URL is <http://www.support.unisys.com>.

Before you install and configure any OS 2200 based system software, it is important that you perform the following tasks, where necessary:

1. Configure the EXEC for the software and regenerate, if necessary.
2. Configure CPCOMM and MCB to facilitate the software.
3. Configure UDS software.
4. Apply any necessary system software changes.

See [Configuring and Regenerating EXEC](#) for more information on performing these tasks.

Configuring and Regenerating EXEC

This subsection describes the configuration of the EXEC.

Configuring the EXEC: Deciding on Application Groups

You must decide the application group or groups on which the Agile Business Suite systems will run by considering the following points:

- If the systems have to run in different application groups, install Runtime into each application group.

The default application group for Runtime is *UDSSRC*, with an application number of 3. Refer to the *Relational Database Server Installation and Configuration Guide* for information on establishing application groups.

- To interface with other (including external) systems, you have to install these systems into the same application group. Refer to the *Integrated Recovery System, Concepts and Facilities Manual* if you require guidelines on deciding whether to place systems in different application groups.

If you intend to interface with external database systems that are under the control of the UDS, the system must be in the same application group as the external system. If you want to interface to a DMS 1100 system, then that system must be in the same application group under the control of the UDS, not DMS 8.

- If you want to run the Runtime in more than one application group, the following products must be either configured or installed for each of the application groups:
 - EXEC (to configure extra application groups)
 - IRU
 - CPCOMM (Application configure statements)
 - TELCON (XEU and DESTSSU statements)
 - MCB
 - UDS Control (UDSC)
 - RDMS (subproduct)
 - UREP (subproduct)

Configuring the EXEC: Creating Application Groups

You might want to regenerate the EXEC to create an application group to run Agile Business Suite. If you have a General Purpose Tailored EXEC (GPTE), an application group already exists. For 2200/400 sites with GPTE, the application group number is 3.

If you do not have an application group, the EXEC must be generated with the appropriate STEP control and AUDIT control SGSs to define the required application group. Refer to the *EXEC System Software Installation and Configuration Guide* for more information and examples.

Queue Items

The number of Queue Items allocated for the Application defaults to 250. Since each active message requires a queue item, this limit can be exceeded, specifically when a large number of MESSAGE; requests are being delivered by the Background run. It is recommended that you increase the number of queue items (for example, to 1000) by using the STEPCONTROL QNBR parameter. This prevents the application that is running out of queue items.

You should use a different QPRIORITY node for your Error Notification Program and different ones for each system or group of systems.

The STEPCONTROL statement must contain at least one PRIORITY, *n*, 0 statement, where, *n* is the QPRIORITY value. This QPRIORITY value is used when configuring the dummy transaction for ROC. A separate PRIORITY statement is required for each of the GLI, NOF, or OFFLINE interfaces that you intend to use.

Using a TIP File to Hold Terminal Records

If you want to use an FCSS TIP file to hold your terminal records instead of an RDMS table and the file is RECOVERABLE, you must include ROLLBACK SGS statements.

Note: *If you require the Rollback Page file, it must also be created and registered with TIP. Refer to the EXEC System Software Installation and Configuration Guide for more details.*

If you install a UCS system and if you want to use an FCSS TIP file to hold your terminal records instead of an RDMS table, you must ensure that you have the UCS TIP Primitives installed. Refer to the *Transaction Processing Installation Guide* for information on generating the TIP with the required options.

The ROLLBACK SGS statements are as follows:

```
STEPCONTROL a ROLLBACK PAGEFILE IS IN FILE n.
```

Where:

- *a* is the Application group number.
- *n* is the TIP file number of the Rollback Page file that is used for quick-look storage when FCSS TIP files are updated.

```
STEPCONTROL a ROLLBACK PAGEFILE ID IS filename
```

This statement specifies the name of the Rollback Page file.

```
STEPCONTROL a ROLLBACK HAS n2 WORDS PER PAGE;  
n3 MEMORY PAGES AND n4 FILE PAGES
```

Refer to the *EXEC System Software Installation and Configuration Guide* for information on calculating the number of words per page (*n2*), the number of memory pages (*n3*), and the number of file pages (*n4*).

Calculating Page Size

To assist in the calculation of page size, the following table shows how the size of Glb.Work affects the terminal record size. The page size must be big enough to contain at least one terminal record. The size of Glb.Work is defined on the Primary Database Options screen. The default size of Glb.Work is 128.

Size of Glb.Work (characters)	Size of Terminal Records (Words)
Up to 132	56
Up to 356	112
Up to 804	224
Up to 1700	448
Up to 3492	896
Greater than 3492	1792

```
STEPCONTROL a ROLLBACK LIMITS ARE ;  
n5 PAGES PER TRANSACTION WITH ;  
THRESHOLD OF n6 PAGES AND ;  
n7 CONCURRENT USERS
```

Refer to the *EXEC System Software Reference Manual* for more information on these parameters.

The following example shows statements for setting up a Rollback Page file:

```
STEPCONTROL 3 ROLLBACK PAGEFILE IS IN FILE 91  
STEPCONTROL 3 ROLLBACK PAGEFILE ID IS APP3  
STEPCONTROL 3 ROLLBACK HAS 896 WORDS PER PAGE ;  
10 MEMORY PAGES AND 200 FILE PAGES  
STEPCONTROL 3 ROLLBACK LIMITS ARE ;  
10 PAGES PER TRANSACTION WITH ;  
THRESHOLD OF 2 PAGES AND ;  
50 CONCURRENT USERS
```

The STNUTIL program, which is used in conjunction with defining FCSS TIP files, commits every 20 records. You have to consider this when calculating the STEPCONTROL ROLLBACK WORDS PER PAGE value and PAGES PER TRANSACTION ROLLBACK LIMIT based on the size of terminal records. This means that if the ROLLBACK PAGE FILE is defined as in the example in the previous step and the size of Glb.Work exceeds 804 characters and there are more than 20 records to process, then errors will occur.

This is based on 896 (words per page) divided by 448 (terminal record size) multiplied by 10 (pages per transaction rollback limit), giving a result of 20 records.

In this example, the error can be avoided if the pages per transaction rollback limit is increased by 1 to 11. An error occurs on the twentieth record as the Rollback page size has its own header information, forcing the twentieth record into the eleventh page.

Configuring the EXEC: EXPRGENVIRON Configuration Parameter

If you are generating a UCS system, you must set the EXEC configuration parameter EXPRGENVIRON to TRUE (the default).

Configuring the EXEC: Parameters for HVTIP

Ensure HVTIP is turned on. You might have to perform a NEWCON EXEC generate. Recommended configuration parameters for HVTIP are listed in the following table:

Parameter	Recommended Value	Description
HVTIP	64	Number of HVTIP libraries.
TPNRTN	7	Maximum number of nested RTN\$s allowed.

Refer to the *EXEC System Software Installation and Configuration Guide* for more information on the TIP configuration.

Configuring the EXEC: Freespace Files

To enable the use of Freespace files, set the FREESPACE configuration parameter to TRUE. This is applicable to ROC flat files only.

Configuring the EXEC: Large Files

If you want to take advantage of the Large Files option (maximum 262,143 positions), set LARGEFILES to TRUE in the EXEC configuration. If you set LARGEFILES to FALSE (the default), the files are limited to 4095 positions.

CPCOMM and MCB Configuration

To configure CPCOMM and MCB for Agile Business Suite, perform the following steps:

1. Install and configure the Message Control Bank (MCB) for recoverable messages, if it is not installed.

Refer to the *MCB Installation Reference Manual* for more information.

2. Ensure the MCB has a User Parameter Area of 32 words or less.

Trigger Characters

You can use the MCB Trigger characters. However, since Agile Business Suite already uses the tilde (~) character for internal use, you should not use it as the trigger character for a system.

Remote Subroutine Server, Builder Server, and Remote Access Server

See [LRSS Configuration Parameters Screen](#) for information on configuring the parameters.

See [DG \(Builder Server\) Configuration Parameters Screen](#) for information on configuring the parameters for the Builder Server.

UDS Software Configuration

You must ensure that the MCBBDI and entry-point (as defined when you installed the MCB) are set in the UDS configuration. You must set the MCB-MSG-BANK-BDI to the value of the afcb1-bdi field of the BDI SGS in the MCB configuration. If incorrect values are set in the UDS configuration, transactions can fail with *MCB error 013* on function 2 (initialize).

When configuring the UDS software, perform the following steps:

1. Set the UDS thread control bank to the maximum. If required, increase its size by entering the following commands in a Data Dictionary session:

```
UPDATE CONFIGURATION config-name.  
REMOVE THREAD-BANK-SIZE.  
ADD THREAD-BANK-SIZE 58880.  
PROCESS CONFIGURATION config-name INSTALL.
```

The thread bank size can be changed when the systems are active. However, before these changes take effect all threads must be stopped. The first thread that restarts must not be a TIP thread.

Set your UDS DCS banks to their maximum size to prevent queuing. Refer to the *Relational Database Server Installation Guide* for more information.

2. Enter the following commands in a Data Dictionary session to increase the size of the UDS DCS bank:

```
UPDATE CONFIGURATION config-name.  
REMOVE DCS-BANK-SIZE.  
ADD DCS-BANK-SIZE 100000.  
PROCESS CONFIGURATION config-name INSTALL.
```

The bank size can be changed when Agile Business Suite is active, but the changes will not take effect until a BEGIN THREAD is encountered after the UDS is idle, that is, when it has no active threads. Refer to the *Relational Database Server Installation Guide* for more information on the DCS-BANK-SIZE parameter.

3. Enter the following commands before installing, if your site has the Data Dictionary sub-product and not the full product:

```
@DD  
DELETE TABLE RDDF$MODEL.  
EXIT.
```

To determine if you are using the Data Dictionary sub-product, attempt to define an entity by entering

```
@DD  
DEFINE ENTITY TYPE X.
```

If you have only the sub-product, an error message appears. If you have the full product, delete the entity by entering

```
@DD  
DESTROY ENTITY TYPE X.
```

Installing AB Suite Runtime for ClearPath OS 2200

Prerequisites

Before installing the AB Suite Runtime for ClearPath OS 2200 you must ensure that both the Application Group and the MCB are in the *UP* state. If Agile Business Suite is configured to use the OLTP, the OLTP TMSB background run must also be in the *UP* state.

Installation Procedure

Runtime is the basic product that enables all other Agile Business Suite software to run. It must be the first product you install.

If you want to change the default configuration parameters, you must use COMUS to perform a configure and build before you install runtime with SOLAR. If you have not previously used COMUS to configure or build, you first have to initialize a COMUS database. Refer to the *COMUS End Use Reference Manual* for more information.

Caution

Agile Business Suite Runtime release 8R0 and Enterprise Application Environment release 3R3 use the same default BDIs. If you still have EAE 3R3 installed, ensure that you install AB Suite 8R0 by using different BDIs.

To install the AB Suite Runtime for OS 2200 using SOLAR, perform the following steps:

(Each of these steps are described in more detail in the following subsections.)

1. If you want to customize Agile Business Suite for your site and change the default configuration parameters, you must perform the following steps:
 - a. Register the Release tape with COMUS.
 - b. Change the default configuration parameter settings.
 - c. Build the Runtime with COMUS.

If you do not change the default configuration parameters, use SOLAR to register and install the Runtime directly from the Release tape.

2. Register the output tape from the build process with SOLAR.
3. Install Runtime by using SOLAR.

Installing Unisys Supplied Changes

Unisys supplies changes by distributing CHGs (Object Changes). These changes can affect the following:

- Runtime
- Any Agile Business Suite component, including the Report Output Control (ROC) system

To install a CHG, see the instructions accompanying the CHG in Tracker (PRIMUS).

To install changes to Runtime Software for each copy of the Runtime, perform the following steps:

1. Insert any Unisys supplied source changes into the COMUS database.
2. Repeat the build and install process by merging the changes into the product at the Build stages.

Refer to the *COMUS End Use Reference Manual* for more information on this process.

COMUS Build Procedure

Customize the installation of Agile Business Suite for your site by performing the following:

Registering the Release Tape with COMUS

To register an OS 2200 based system with COMUS, perform the following steps:

1. Log on to DEMAND.
2. Specify the COMUS qualifier, by entering

```
>@QUAL qualifier
```

where, *qualifier* is the value that is specified when the COMUS database is created.

3. Initiate COMUS by entering

```
>@COMUS
```

4. Register with COMUS by entering

```
>REGISTER REEL=reelnum PRODUCT=ABSUITE,8R0
```

where, *reelnum* is the tape identifier of the Release tape. The Release tape is unlabeled and the default tape characteristics are assumed.

COMUS assigns the tape and waits for you to mount it.

When COMUS completes the registration task, it displays one of the following messages:

```
UPDATE TASK COMPLETED
INSERT TASK COMPLETED
```

To check the result of the register process, look at the print files produced under the runid that initiated the register. These print files contain information specific to this release, including (in the case of an Interim Release) the details of all Object Changes (CHGs) patched by this release.

Changing the Default Configuration Parameters

You must configure and build the parameter changes, even if you accept the default settings.

To change the configuration parameters for your site, perform the following steps:

1. Start the configuration process by entering the following command to update the configuration parameters for the Runtime:

```
>CONFIGURE MODE = UPDATE
```

A list of the available Configuration Sets appear.

A Configuration Set is a release of a product or a group of products or sub-products that are installed together. There can be more than one Configuration Set for a product. For example, if you want to install in more than one application group, you have to create a Configuration Set for each application group.

If the COMUS database is not used before, a message appears indicating that no Configuration Sets exist.

2. Create a Configuration Set, by entering the following COPY command:

```
COPY PRODUCT = ABSUITE LEVEL = 8R0 TO = runtime
```

where, runtime is the Runtime name used in the BUILD.

COMUS redisplay the Configuration Set Selection screen (after you execute the COPY command.)

3. Enter the number associated with the set you have just created and transmitted.

The Product Selection screen appears displaying the following:

PRODUCT	LEVEL
1 ABSUITE	8R0

This screen is used by the Configuration Sets containing more than one product.

4. Enter 1 to select ABSUITE 8R0.

This displays the Configuration Process Main Menu screen. Throughout the configuration process, you can obtain help information by typing a question mark character (?) either in the top left-hand corner (to obtain general information about the whole screen) or in column 1 of a field position (to obtain information about that field).

The Main menu displays the following options and each option displays additional screens:

- 1) General Configuration Parameters (GENERAL)
 - 2) Processor File Names (FILES)
 - 3) Common Bank Attributes (BANK)
 - 4) HUB configuration parameters (HUBPARAM)
 - 5) OLTP configuration parameters (OLTPPARAM)
 - 6) LRSS configuration parameters (LRSSPARAM)
 - 7) DG (Builder Server) configuration parameters (DGPARAM)
5. Enter the associated number from the Main Menu to display the current values for any of the above group of parameters. To change a parameter, overtype its existing value on the specific parameter screen.
- Some of the parameters for these options are spread over more than one screen.
- To view these, enter a plus sign (+) to display the next screen in the sequence, or enter a minus sign (-) to display the previous screen.
6. Transmit to effect the changes after you make all changes to a specific screen.
 7. Enter *BACK* to return to the Main Menu to select another group of parameters.
 8. Enter *PROCESS* and transmit when you are satisfied with all the changes. You can enter this command from any screen.
 9. Enter *OMIT* to discard the changes you have made.
- The Main Menu appears.
10. Enter *END* (or *E*) to terminate the configure process.
- An error message appears if the configure process is not successful.
11. Enter the *EXIT* command to terminate the current COMUS session.

Building the Runtime

To build Runtime, perform the following steps:

1. Start the Build process by entering the following command during a COMUS session:

```
>BUILD ABSUITE, 8R0
```

The first time you build Runtime, you have to enter the default parameters.

2. Enter the required values or accept the default values.

Refer to the *COMUS End User Reference Manual* for more information.

A set of suggested values that you can enter for your initial build is shown in the following table:

Item	Suggested Value or Action
Runtime name	Enter the Runtime name you specified when configuring the software
Project Id	<i>ABSBUILD</i>

Item	Suggested Value or Action
Runid	<i>BLDABS</i>
Run Options	Transmit a space
Run priority	Transmit a space
Tape equipment	For example, <i>VTS</i>
Tape assign option	<i>TF</i>
Generation type	<i>TAPE/TAPE</i>
Permanent SGSs	Transmit a space
Maximum	<i>9999</i>
Maximum pages	<i>99999</i>

During the Build process, a number of messages appear. The following messages require you to enter a response:

- Generation id?
Enter a meaningful identifier for this build.
- Generation heading (<>)?
Enter a heading for the print output created by the Build process.
- What is the name of the Runtime you want to build?
Enter the name of the Runtime you want to build. If you are accepting all the configuration defaults, transmit to accept the default name from the Release tape. The default Runtime name on the Release tape is ABS8R0. The default configuration parameters are described in "COMUS Configuration and SOLAR Installation Parameters". If you enter a name, it must be the name you supplied in the General Configuration Parameters.

Notes:

- *The maximum length of the Runtime name entered in the COMUS configuration screens is eight characters.*
 - *If you have created a configuration set in COMUS and used the default Runtime name in General Configuration Parameters, the name must be entered to accept the values in the COMUS database. If not, the name in the tape will be used.*
3. The Build process creates an ECL runstream. You can view this runstream before execution. (If you have to modify the runstream, you must exit COMUS and use an editor).

If you are satisfied with the runstream, instruct COMUS to start the batch job that generates a new (unlabeled) master tape. (Disk to disk BUILDS are not supported.)

The BUILD TASK COMPLETED message appears when the processing is complete.
 4. Review the output from the batch job and check for errors, to ensure the Build is successful.

The output is directed to the default print queue and the last page identifies the errors, if any.

Most of the output is directed to the PRNTF\$ file and is copied to the output tape. The remaining output is printed.

Installing Runtime

About Runtime Release Tape

The Runtime Release tape, supplied as an unlabeled 18 track uncompressed tape, contains the following files:

File	File Name	Description
1	TPF\$	COMUS utility file
2	UTIL\$	Agile Business Suite Utilities
3	ALIB\$	Common Bank Absolutes and subsystem object modules
4	OLIB1\$	Relocatables and object modules used for Build
5	OLIB\$	Relocatables
6	OMLIB\$	Extended Mode Object Modules
7	SLIB\$	Source elements
8	PCF\$	OS 2200 based system changes
9	PRNTF\$	Build print file
10-14	ROCSYS	Report Output Control (ROC) system object files
15	GLOBALST	Skeletons used by generate
16	GLOBALSG	Skeletons used by generate
17	CODES	Sample CODES file
18	DGUTIL\$	Builder Server file
19	U\$SCRREL	Utility Program Screens
20-23		COMUS files

Installing with SOLAR

To run the SOLAR installation of Runtime, perform the following steps:

1. Register the Release or Output Tape
2. Install from Registered Packages
3. Modify the Runstream
4. Set Up Special Installation Privileges
5. Check the Installation Verification Procedure (IVP)

Following is a detailed description of these steps:

Registering the Release or Output Tape

To register the release tape or the output tape from the build process with SOLAR, perform the following steps:

1. Initiate SOLAR by entering, the following:

```
>@SOLAR
```
2. From the SOLAR Main menu, move to the **Register** field and transmit.
The Package Information screen appears.
3. Enter the source media containing the output of the COMUS Build process. For example, if you have an unlabeled tape 23792c, you have to enter this in the **Reel Ids:** field.
The Runstream Information screen appears.
4. Copy the runstream and exit SOLAR.
5. Enter the copied runstream and parameters as follows:

```
runstream,,,account/userid
```

The userid must have certain privileges. See "Setting Up Special Installation Privileges" for details on the user ID privileges.

Installing from Registered Packages

To install Release 8R0 from the registered packages, perform the following steps:

1. Initiate SOLAR by entering, the following:

```
>@SOLAR
```
2. From the SOLAR Main menu, move to the **Software Installation: Registered Packages** field and transmit.
The Package Information screen appears.
3. Locate the screen containing ABSUITE 8R0.
4. Mark the ABSUITE 8R0. tape that you registered and press the **F8** key.
5. Move to the Mode you want to install and press the **F5** key.
The Runstream Information screen appears.
6. Copy the runstream and exit SOLAR.
7. Enter the copied runstream and parameters as follows:

```
runstream,,,account/userid
```

The userid must have certain privileges. See “Setting Up Special Installation Privileges” for details on the user ID privileges.

Modifying the Runstream

If you want to modify the runstream, you must exit SOLAR and use an editor. If you are satisfied with the runstream, inform SOLAR to start the batch job. The batch job reads the product master tape created by the Build process and installs the Runtime.

Setting Up Special Installation Privileges

You require special privileges to perform the install process. For example, the MAKE-TABLES runstream updates the runtime*PERM\$SGS file with Integrated Recovery Application information. The runstream therefore requires the necessary privileges to accomplish this. Check with your site security administrator.

Refer to the *COMUS End Use Reference Manual* for a summary of the required privileges. The Common Bank Reload privilege is required to install Agile Business Suite 8R0.

The user ID used to register and install Runtime must have the necessary privileges to perform the SOLAR installations. Refer to the *SOLAR End Use Reference Manual* for information on the required privileges.

Furthermore, the security environment must be set up properly for the LINC\$RTS subsystem to function correctly. Refer to the *OS 2200 Software Products Installation Guide* for guidelines on setting up the security environment for Object Module Subsystems.

Runtime contains both chameleon and protected subsystem types. The user ID of the owner of the ALIB\$ file that contains the subsystem definition elements must have the following subsystem security attributes:

Parameter	Value
User-id Name	-ABSUITE- Note: -ABSUITE is the recommended user ID.
Record Access	Semiprivate
Attached ACR Name	EXEDEL
ACR Arguments	Execute: Public Delete: Userid EQ SUBSYS-ADMIN
Run Mode	None
Processor Privilege	Read Execute GRS

Parameter	Value
Access Privilege	Trusted
Sharing Level	Application
Clearance Level	Minimum = 0, Maximum = 0
Compartment Set	Maximum = NULL, Default = NULL
Trusted Privileges	None
Other Privileges	SSGAP
ERs, CALLs	None
File ACR Name	PUBRD
File ACR Arguments	Read: Public

Checking the Installation Verification Procedure (IVP)

The Installation process contains an IVP. The IVP checks if the Runtime is installed successfully by checking if all files, RDMS tables, and Common Banks are set up correctly.

If the IVP fails, you can check the success of the installation procedure by reviewing the output from the SOLAR installation run and checking for errors. The last page identifies any errors that might have occurred.

The output from the installation shows the number of elements that were created in the SOLAR*DIAGNOSTIC file.

Check if there were any errors encountered during the installation. If there is any problem, inspect the PL-DIAGINFO/timestamp element with an editor to determine the cause of the problem.

Installation Modes for Setting Up the HUBs

The HUB feature handles external Automatic Entries, including those between hosts. A HUB is defined by the LINC\$HUB BDI and the HUB identifier in the COMUS Configuration Set. One HUB can comprise multiple Runtimes.

Use the MODE parameter in the SOLAR installation of the Runtime to define the Runtime you are installing.

If you are planning an interhost communication, this procedure must be followed on each host. That is, there must be a HUB Common Bank for each host.

For interhost Automatic Entries, you are required to supply an element (HUB\$SGS) containing the SGS parameters that define the host names and addresses of the network.

This is a post-installation procedure.

One Runtime is nominated as the controller of the HUB. Install this environment first. Select the HUB mode on the SOLAR installation screen.

When additional Runtimes are installed into the same HUB (that is, in the same intersystem communication network), select the *LINC* mode field on the SOLAR installation screen. The Runtimes within a HUB are linked by having the same HUB ID and HUB common bank BDI during the COMUS configuration.

The LRSS feature allows Developer debugging and testing of a system to access external subroutines (using the CALL command) on the target host. For OS 2200 hosts, this allows access to any non-HVTIP installed subroutine on the host during Developer debugging and testing. Typically, these subroutines are interfaces to legacy AB Suite systems.

You can install the LRSS only if you specify a BDI in the COMUS CONFIGURE (menu entry 7).

- Mode LINC - Install Agile Business Suite
- Mode HUB - Install Agile Business Suite and HUB
- MODE LRSS - Install Agile Business Suite and LRSS
- MODE ALL - Install Agile Business Suite, HUB, and LRSS

The default mode is *HUB*.

Notes:

- *All Runtimes must belong to a HUB. As a result, for the first Runtime you install, you must select the HUB mode, even though it might be the only environment to be used.*
- *The LRSS feature for Developer debugging and testing will be implement in a future release of AB Suite.*

Reinstalling or Switching the Controller

You can reinstall or switch the controlling Runtime, by performing the following steps:

1. Ensure that all Background Runs for the HUB are down during this procedure (they all share the same common bank).
2. Install the intended controlling environment. Select the *HUB* mode. During this process, the old controller will be uninstalled if the same BDI value for the LINC\$HUB common name is used.
3. Reinstall the old controller when the switch is complete. Select the *LINC* mode.

Installation Modes for Builder Server

The Builder Server is part of the Runtime installation. It communicates with the Builder Client on a Developer workstation through the TCP/IP sockets to allow generation of systems directly from the Developer environment. Multiple Builder Servers can be installed on a single OS 2200 host.

Use the MODE parameter in the SOLAR installation of the Runtime to define the Runtime you are installing. The following modes include the Builder Server in the Runtime installation:

- HUB & DG
- LRSS & DG
- LINC & DG
- ALL & DG

The default BDI for the Builder Server is 201643.

Note: A distinct BDI must be assigned to each Builder Server installed on a single OS 2200 host.

Configuring the Builder Server

Use the configuration element DIRGEN\$<DG Configuration Identifier>*DGUTIL\$.CONFIG to configure the Builder Server. For example, if the DG Configuration Identifier is *D*, you have to enter the following:

```
DIRGEN$D*DGUTIL$.CONFIG
```

The default DG Configuration Identifier is A.

To change the port number, use any ClearPath OS 2200 editor and change the PORT parameter to the desired number in the form PORT nnnnnn. After changing the port number the server must be restarted.

The default port number is 7775.

Note: A distinct Port Number must be assigned to each Builder Server installed on a single OS 2200 host.

Connection Status

You can check the current connection status, port number, and DG Configuration Identifier of the server by using the following keyin at the Operators Console or by using a Demand terminal in CONS mode:

```
generated runid STATUS
```

where, generated runid is the DG<DG Configuration Identifier>TCP. For example, if the DG Configuration Identifier is *D*, you have to enter

```
DGDTCP
```

Note: When a Builder Server is aborted during a run, the generated runid is incriminated to avoid duplicate runid. Therefore, if DGDTCQ has to be aborted, DGDTCQ will be the generated runid.

Starting the Builder Server

Use the following keyin to start the Builder Server:

```
ST DIRGEN$x*DGUTIL$.DGxTCP,,,account/userid
```

This also starts the TCP Server that initiates the Session Controller and Scheduler. The runid for the Session Controller and Scheduler is DGxCTL (where, x is the DG Configuration Identifier).

Note: *It is the responsibility of the user to manually control the starting of any generate tasks whose start time has passed when the server was down.*

Stopping the Builder Server

The following keyins terminate the Builder Server session:

- Allows the existing connections to complete before terminating the server.

```
generated runid STOP
```

- Terminates the server immediately.

```
generated runid TERM
```

Installing Runtime with the XTC

The XTC systems consist of two or more OS 2200 Series hosts, special interhost communications links, such as a Host LAN Controllers (HLCs), shared mass storage subsystems, and Record Lock Processor (RLP). The RLP keeps track of the current resources in use. The XTC uses the RLP to coordinate shared database operations across all hosts.

XTC TIP

The XTC TIP, through the use of shared application groups, enables you to share the TIP and HVTIP applications across multiple hosts. This functionality is controlled by the EXEC configuration tag, MHTIP. Within a shared application, the XTC TIP enables you to share access to transactions and databases between multiple hosts.

XTC UDS

The XTC UDS is a facility of Universal Data Systems that permits the sharing of DMS, SFS, and RDMS databases across the hosts of an information hub. The XTC UDS also uses the RLP to track resource usage across all hosts.

About Shared and Local Application Groups

On an XTC system the valid OS 2200 based application groups are

- Local
- Shared

You can install the Runtime on local or shared application groups. When configuring the Runtime, specify the application group in which it will run. If the application group type is local, systems that are part of that copy of Runtime will be confined to a single host. If the application group is shared, the systems will be available on all hosts.

Local Application Groups

Systems in local application groups operate normally but with one exception.

If the host has MHTIP (XTC TIP) configured, all the HVTIP library files must be cataloged on the shared mass storage and registered in the shared directory, even if the HVTIP system itself operates in a local application group.

For Agile Business Suite systems, this means for hosts with the MHTIP configured, all the HVTIP libraries are cataloged on shared mass storage.

For systems in a local application group, this means that the OBJECT PACK specification will not be honored for the HVTIP library. Instead, the HVTIP library will be cataloged on fixed shared mass storage as the removable disks specified for use in a local system are local removable disks. Due to the MHTIP requirement, the HVTIP library cannot be cataloged on the same disks as the other object files for the system.

Shared Application Groups

When the Agile Business Suite system is installed in a shared application group, all files (and any defined packs) are cataloged as shared on the shared mass-storage and are registered in the shared directory. While the system is operating, the XTC UDS uses the XPC/RLP to coordinate the updates and the locks on all hosts.

Agile Business Suite handles all the details associated with shared systems. A shared application group is selected automatically by running in the appropriate Runtime.

Installing Runtime on a Shared Application Group

In an XTC environment, use SOLAR to install the Runtime on the same shared application group on each host.

Follow the COMUS configure and build, and SOLAR installation procedures for the first host. The first installation creates the RDMS tables for the total environment on the shared mass storage.

The output from the configure or build on the first host is date or time stamped. You should install the same output tape on all hosts in the XTC environment.

When you install it on another host, the system detects from the date or time stamp that you are installing the same shared Runtime and the RDMS tables are not created again.

If the date or time stamp does not match for the existing shared environment, then the RDMS tables are built for a new Runtime. In this case, before you install, you must stop all the Background Runs on all the hosts.

Installing Runtime with PAEXEC

Partitioned applications can be switched between hosts in a PAEXEC environment, although an application can only be running on one host at a time.

You must install Runtime on both the hosts in the PAEXEC configuration.

During the installation of Runtime, RDMS tables for applications that can be switched are catalogued on mass-storage.

You must ensure that a shared removable mass-storage device is used in the COMUS configuration, if removable packs are used on the hosts.

Before Using Runtime

After installing Runtime, you must perform the following tasks before using it:

Set Up the Library

Ensure that an HVTIP library is created to hold the Runtime. This can be either a shared library or a non-shared library.

If you are using a shared library, run the Runtime Utility (LRU) by using the following statement:

```
@runtime*UTIL$.LRU SHAREDLIB
```

The following prompt is returned from the LRU:

```
Please enter PACK - to pack an existing library
or BUILD - to build/rebuild a shared library
or DELETE - to delete an existing shared library
```

Enter *BUILD*.

Turn on TIP Transaction Processing

Use the FB command to ensure that the FB OP\$MAIN parameter is on. This effectively turns the TIP transaction processing to ON. Refer to the *TIP Installation Guide* for more information.

Define a TIP Error Handling Program

TIP requires an error handling program to receive recoverable messages that cannot be successfully processed. The STEPCONTROL EXEC SGS defines the QPRIORITY of the error handling program.

If an error handling program is not created and the STEPCONTROL SGS defines the same QPRIORITY for the non-existent error handling program as for the system, a transaction error can stop the entire system.

A sample of an error handling program is provided in the COMUS file (file1) on the Release tape. A sample ECL to map the error handling program is also provided in this file. The element names are MCBSE1 and MCBSE1 / MAP.

To copy file 1 from the Release tape to a file, where reel is the reel number and type is the tape equipment type, execute the following ECL:

```
@ASG,TJ ABSUITETAPE.,type,reel
@CAT,P file.,F///1000
@COPY,G ABSUITETAPE.,file
```

Refer to the *MCB Installation Reference Manual* for more information on error handling programs.

Set Default Page Size

The default page size (MAX-PAGE-SIZE) parameter for the Integrated Recovery Utility (IRU) should be set to at least 7168 to allow IRU to back up all the RDMS tables. Refer to the *Relational Database Server Installation Guide* for more information on this parameter and on changing the parameter.

Starting Background Runs

The Background Run and the HUB Background Run should be active before you install and use the other Agile Business Suite products.

To start a runstream from the system console, enter the following command:

```
ST qualifier*file.runstream,,,account/userid
```

The userid must have the special installation privileges. See [Installing with SOLAR](#) for more information on setting up the special installation privileges.

Depending on the software configuration, you might be able to abbreviate the command as follows:

```
ST runstream
```

The name of the runstream that starts the Background Runs is defined when the Runtime software is installed. By default, it is A8R0. This runstream is placed in SYS\$LIB\$*RUN\$. See [COMUS Configuration and SOLAR Installation Parameters](#) for more information.

Reinstalling Runtime

You might have to reinstall Runtime for the following reasons:

- Updating to a new release of Agile Business Suite
- After upgrading the operating system (recommended)

Reload TIP Library

If you are already running the TIP, you might have a runstream in SYS\$LIB\$*RUN\$ that reloads the HVTIP libraries after a system reboot. To this runstream add a reload of the TIP library associated with each of the systems.

Enter the following ECL to load or reload an HVTIP library:

```
@XQT,MUZIX tiprun$-file.TPUR
LOAD nn
```

Where, *nn* represents the HVTIP library number.

If you have the Application Recovery Feature (ARF) turned on (by using the TIP ON system keyin), then the reloading of HVTIP libraries is automatic.

A runstream is available with Runtime to reestablish a system TIP environment. Enter the following from a Demand session:

```
@runtime*UTIL$.LRU RECOVERTIP
```

A message appears prompting you to enter the system name. Entering the correct system recovers its TIP environment.

Note: If you perform a valtab build or jump key 7 or 13 boot, you have to reestablish your TIP environment by running recovery for all your Systems.

Procedure for Reinstalling Runtime

To reinstall Runtime, perform the following steps:

1. Ensure that no one is using Runtime when you are reinstalling the product.
2. Close down all systems by executing the following CLOSEDOWN program:

```
@environment*UTIL$.LRU CLOSEDOWN,$ALL
```

3. Terminate the HUB Background Run by entering the following command from an operator console:

```
HUBid TERM
```

Where, *id* is the HUB identifier that was specified when configuring the Runtime.

4. Terminate the Background Run by entering the following command:

```
runtime STOP
```

Where, *runtime* is the Runtime name.

RDMS Tables

Table	Contain Details of ...	Saved As
runtime_SCHEMA.LSYS	All systems configured within the Runtime	runtime*SAVE-LSYS

Table	Contain Details of ...	Saved As
<i>runtime_SCHEMA</i> .SECURITY	Security that you have loaded for all systems within Runtime	<i>runtime</i> *SAVE-SEC
<i>runtime_SCHEMA</i> .SECURINT	Security that you have loaded for the Host Builder	<i>runtime</i> *SAVE-SECINT
<i>runtime_SCHEMA</i> .PIDRANGES	TIP Stations	<i>runtime</i> *SAVE-RANGES
<i>runtime_SCHEMA</i> .CONFIG	COMUS Parameters	<i>runtime</i> *SAVE-CONFIG
<i>runtime_SCHEMA</i> .STNDEFAULT	Initial setup information for station records	<i>runtime</i> *SAVE-STNDEF
<i>runtime_SCHEMA</i> .SERVICES	Relationships between the OLTP service names and the systems they are part of	<i>runtime</i> *SAVE-SRVCES

If saved files are found to exist at the beginning of an install, it is assumed that an earlier install has failed. In such case, the current install stops after displaying a detailed message. Therefore, you have to check the save files. If they are empty, delete them and restart the install. If they contain valid data and the system tables are empty, perform the following:

```
@SETC 011/S4
@ADD runtime*UTIL$.MAKE-TABLES
```

Handling Unsaved RDMS Tables

The following data is not saved and restored when reinstalling Runtime:

- *runtime_SCHEMA*.ACCEPTS
- *runtime_SCHEMA*.REPORTINFO
- *runtime_SCHEMA*.REPORTSRUN
- *runtime*

There can be implications in the fact that these tables are not saved when reinstalling Runtime. If you have a Report that went into extended report recovery immediately before you reinstalled the Runtime, you would lose the information in the Report when the Report is recovered under the new Runtime.

See [Files Created by Agile Business Suite](#) for more information on reports.

Installing Additional Copies of Runtime

You can install more than one copy of Runtime. For example, you might want to run Agile Business Suite in more than one application group.

To install an additional copy of Runtime, perform the following steps:

1. Create a new Configuration Set by specifying a different Runtime name and Configuration Set name.
2. Configure the Runtime (as described earlier in this subsection) followed by the Build and Install tasks.

The Runtime name, the Common Bank BDIs, and the Background Run ID must be unique for each Runtime. If you are installing the Runtime on a different application group, you have to change the application name, the application number, and the Library file names for the MCB and RDMS.

3. Install the Runtime by selecting the LINC mode, if the additional Runtime is to be part of an existing HUB network.

Caution

It is not recommended to install more than one Builder Server per host per Agile Business Suite release.

Uninstalling Runtime

To uninstall Runtime from OS 2200, perform the following steps:

1. Remove all active systems within the Runtime by using the **REMOVESYS** option of the Runtime Utility (LRU).

Use the `@runtime*UTIL$.LRU SYSCHEK,$ALL` command to obtain a list of all installed systems.

2. Terminate the Background Run by entering the following command from an operator console:

```
runtime STOP
```

Where, *runtime* is the name of the Runtime.

3. Remove Runtime schema details from Meta Services Engine or RDMS. To do this, enter the following commands from the Demand session:

```
@SETC 033/S4  
@ADD runtime*UTIL$.MAKE-TABLES
```

4. Use SOLAR to remove the rest of Runtime and LINCELMS.

Select the **REMOVE PRODUCTS** option from the main menu. You can ensure you are removing the desired Runtime by pressing the **F10** key from the Product Selection screen.

Note: For PAEXEC systems, you will have to perform this step for each of the switchable application groups.

5. Enter the following command, from the Demand: session:

```
@CYCLE runtime*LINCELMS.,0
```

COMUS Configuration and SOLAR Installation Parameters

This section describes the parameters required for each stage of COMUS configuration and SOLAR installation of the Agile Business Suite software. See [Installing AB Suite Runtime for ClearPath OS 2200](#) for instructions on these stages.

Configuration parameters and defaults for installing a system that will communicate with the OLTP environment.

Stages of the Configuration and Installation Process

The stages of the COMUS configuration and SOLAR installation process are listed in the following table:

Stage	Process	Description
1	Register (COMUS)	Register the Release tape with COMUS.
2	Configure	Set the configuration parameters to customize for your site.
3	Build	Build a copy of Runtime.
4	Register (SOLAR)	Register the output of the Runtime with SOLAR.
5	Install	Install a copy of the Runtime.

You can change the configuration, and rebuild or reinstall with new parameters at any time after installing the Runtime.

COMUS Configuration Main Menu

The COMUS Configuration Main Menu enables you to navigate to the following configuration screens:

- General Configuration Parameter Screens
- Processor File Names Screens
- Common Bank Attributes Screen
- HUB Configuration Parameters Screens
- OLTP Configuration Parameters Screen
- LRSS Configuration Parameters Screen
- DG (Builder Server) Configuration Parameters Screen

From the Home position, enter a number for the group of configuration parameters you want to access and transmit. The screens and individual parameters for each of these groups are described in the following subsections.

Hints on Navigating and Online Help

You can access the Configuration parameter screens from the Configuration Main Menu screen.

For online help, enter a question mark (?) at the top of the screen and transmit.

Some of these screens have continuation screens. To display a continuation screen, enter the plus sign (+) at the Home position. To return to a previous screen from a continuation screen, enter the minus sign (-) at the Home position.

To return to the Configuration Main Menu, enter b in the Home position of any screen.

General Configuration Parameter Screens

Use the General Configuration Parameter screens to enter the basic parameters for Runtime. The various General Configuration Parameter screens are described in the following subsections.

General Configuration Parameter Screen 1

This subsection describes the fields on the General Configuration Parameter Screen 1.

Runtime Name

Enter the name for the Runtime you are configuring. You can install more than one copy of Runtime. The default name is *ABS8R0*.

Each Runtime name must be unique and can contain up to eight characters, the first of which must be alphabetic. The Runtime name is used as a qualifier for your OS 2200 based production files and is the name you use with the BUILD command. The maximum length is eight characters to prevent the *runtime\$Lxx* and *runtime\$Rxx* Common Bank names from exceeding the maximum length of 12 characters.

It is advisable to use the same name as you specified for the COMUS Config Set Name.

Background Run RUNID

Enter the name of the runstream created in *SY\$LIB\$*RUN\$* to start the Background Run. The value that you enter is the run ID of that run. This name must be a unique run ID of up to six characters.

It is advisable to use the Runtime name for the Background Run ID.

The default value is *A8R0*.

Configuration Description

Enter an optional description for a specific configuration. Up to three lines of text are available.

Each description line can be up to 32 characters.

The default is spaces.

Application Name

Enter the name of the Application Group in which you want to install the OS 2200 based Runtime. The default is *UDSSRC*.

The Application Name identifies a recoverable element to the operating system, the recovery system (IRU), and the data manager (UDS).

Application group names have an associated Application Number, which is also a configuration parameter. The Application Number you specify must relate to the application name that you enter. Consult your Site Administrator about the choice of Application Group.

Real Application Names are required as aliases are not valid.

Application Number

Enter the number of the Application Group in which you want to install the OS 2200 based Agile Business Suite. The valid range is 1 through 16. The default value is 3.

The Application Number you specify must relate to the Application Name. See "Application Name" parameter for more details.

HVTIP Base Library Number

Enter the base TIP file number for the HVTIP libraries. This number can contain up to four characters and must match the value of the TPLIB operating system configuration parameter in the EXEC generation. By default, the value is 17.

Consult your Site Administrator about the base TIP file number for the installation.

System Files Equipment

Each copy of Runtime maintains control information in the RDMS tables. In System Files Equipment enter the equipment type of the unit where the associated RDMS storage area is to be located. The default is F that locates the files on fixed mass storage.

Note: *Several environment files are created external to COMUS and these files are also created on the specified equipment type.*

You can enter up to eight characters. See "System Files Packids" parameter for more details.

System Files Packids

If you leave this parameter blank (the default), the storage area is placed on fixed mass storage. You can enter a maximum of 32 characters.

Enter the packid of the unit where the Control storage area and other associated files are to be located.

If multiple packids are required, enter them consecutively by separating them with a slash character (/) as shown in the following example:

PACK04/PACK06/PACK01/PACK99

The packs specified have the same equipment type that you specify in the System Files Equipment parameter.

System Files ACR Name

Control information for Runtime is maintained in the RDMS tables. In System Files ACR Name, enter the ACR name to be used when cataloging the file containing these tables.

You can enter up to six characters. Additional equipment files also have this ACR on the catalogue. Refer to the *SIMAN Reference Manual* for more information.

Note: Security for RDMS tables should be established with care, as all transactions have to pass this ACR.

General Configuration Parameter Screen 2

This subsection describes the fields on the General Configuration Parameter Screen 2.

Common Bank BDI Parameters

Common Bank BDI parameters for the Configure stage are described as follows:

LINC\$TABLES BDI

Enter the BDI for the LINC\$TABLES Common Bank. You must enter all seven characters, including the leading zero. The LINC\$TABLES Common Bank contains data structures that are used to coordinate the operation of Runtime.

Each copy of Runtime must have a separate set of Common Banks. It is advisable that LINC\$TABLES and LINC\$SUBS use consecutive BDIs. For example, 0402672 and 0402673.

The default value is 0402676.

LINC\$SUBS BDI

Enter the BDI for the LINC\$SUBS Common Bank. You must enter all seven characters, including the leading zero. The LINC\$SUBS Common Bank contains subroutines used in the execution of your systems.

Before entering these BDIs, check that they are not already in use. These numbers are shown as a sample set in the Relational Database Server Installation Guide, for application group 8. Consult your Site Administrator about the choice of BDIs. See "LINC\$TABLES BDI" parameter for more details.

The default is *0402677*.

LINC\$EMCB BDI

Enter the BDI for the LINC\$EMCB Common Bank. You must enter all seven characters, including the leading zero. The LINC\$EMCB Common Bank contains subroutines used in the execution of the UCS systems.

The default is *0404615*.

LINC\$STN BDI

Enter the BDI for the LINC\$STN Common Bank. You must enter all seven characters, including the leading zero, in extended mode format (for example, 020xxxx). The LINC\$STN Common Bank contains the subsystem used to store station data associated with Glb.Work in memory. Other S_T_N station data will continue to use the RDMS table or FCSS file.

The default is *0205112*.

LINC\$RTS BDI

Enter the BDI for the LINC\$RTS Common Bank. You must enter all seven characters, including the leading zero, in extended mode format (for example, 020xxxx).

The LINC\$RTS Common Bank contains the UCS support routines created as a chameleon fast-load self-contained subsystem (FLSS), a shared subsystem that allows fast loading of local unshared data.

The default is *0205467*.

General Configuration Parameter Screen 3

This subsection describes the fields on the General Configuration Parameter Screen 3.

EIS Capable Host

Enter Y to specify that Runtime has to run on an Extended Instruction Set (EIS) machine. EIS is a hardware feature that gives faster character handling and is available on all OS 2200 based machines.

Enter *N* if EIS does not apply. The default is *Y*.

Print Queue for Error Dumps

Enter the print queue in which you want any TIP printed output or post-mortem dumps to be placed. You can enter up to four characters. The default is *PR*. This value applies to all the OS 2200 based systems within Runtime. However, it can be overridden at system level.

Network Host ID for this System

Enter the Host ID of the machine the Runtime runs on, as defined in the TELCON software. This is used in the global host parameters enabling the OS 2200 based systems running on other hosts to access the OS 2200 based system.

You can enter up to six alphanumeric characters. The value entered is automatically stored in the built-in segment attribute, Glb.SelfHost and is automatically moved to Glb.OriginHost when an external Automatic Entry is performed.

The default value is the six space characters that does not provide a host ID. That is, the system is not accessible to the OS 2200 based systems running on other hosts.

On the XTC systems, select one Network Host ID to represent all the closely coupled hosts. For example, if the system consists of hosts with network IDs *NY01*, *NY02*, *NY03*, and *NY04*, you can select *NY01* to represent the entire system. This causes the entire XTC system to be treated as a single host.

ROC Transaction ID

Enter the TIP transaction ID to be used to sign on to the ROC.

Up to six alphanumeric characters can be used. The default is *RT8R0*.

ROC Database Name

Enter the database name to be used for the ROC. The name is used as a qualifier for the ROC database files. The name must not exceed seven alphanumeric characters. The default is *RD8R0*.

ROC Spooler Transaction ID

Enter the TIP transaction ID to be used by the ROC spooler to receive transaction input. You can enter up to six alphanumeric characters. The default is *RQ8R0*.

ROC Environment Name

You can use the ROC system that runs in a different copy of Runtime to the Runtime you are installing. In the ROC Environment Name field, enter the name of the Runtime in which ROC is to run. You can enter up to ten characters. The default is spaces, which is the Runtime you are currently installing.

ROC Spooler Queuing Node

Enter the Queue Priority node used by the ROC Spooler to receive transaction input. Node numbers can be in the range 1 through 99999. The node used must be defined before in an EXEC gen with a QMAX parameter of zero. This node must not be in current use.

The default is *10*.

Maximum Number of PIDs

Enter the maximum number of terminals that can be simultaneously connected to systems within the current copy of Runtime. You can enter up to five numeric characters.

This parameter controls the size of the ACTIVEPIDS table in the LINC\$TABLES Common Bank that is used to scan for terminals that are timed out.

The default is *1000*.

Idle Terminal Timeout (min)

Enter the time (in minutes) that a terminal is to remain in idle status. You can enter up to four numeric characters. After this time a BYE will be automatically issued by the Background Run to sign the terminal off the system.

Multiple PIDs on the same physical terminal are monitored separately.

The default is *30*.

Timeout Check Interval (sec)

Enter the time interval (in seconds) between checks for idle terminals. This value specifies how often the Background Run scans through the ACTIVEPIDS table.

The default is *60*.

Caution

Unsuitable values for this parameter can affect performance.

Clear AUX Area in MCB Packet

Enter Y if you have an XIS or AIS environment. This informs the MCB not to call its error handling routine.

The default is *N*.

Processor File Names Screen

Use the Processor File Names screens to name the various software packages used to operate or build your copy of Runtime.

Entering Parameters

All parameters have a maximum length of 25 alphanumeric characters.

Processor File Names Screen 1

This subsection describes the fields in the Processor File Names Screen 1.

COBOL Compiler (@ACOB)

Enter the name of the COBOL compiler file. Do not enter a trailing period after the file name.

The default is `SYS$LIB$*ACOB`.

UCOB UCS COBOL Compiler

Enter the name of the UCOB COBOL Compiler file.

Do not enter a trailing period after the file name. The default is `SYS$LIB$*UCOB`.

Note: If a UCOB compiler file is specified, the U—U Spec is always compiled with the UCOB compiler in addition to the ACOB. This results in the UCS Reports to link correctly.

Collector (@MAP)

Enter the name of the Collector processor file. Do not enter a trailing period after the file name.

The default is `SYS$LIB$*MAP`.

Data Dictionary (@DD)

Enter the name of the Data Dictionary processor file. Do not enter a trailing period after the file name.

The default is `SYS$LIB$*UREP`.

ACOB TIP Library

Enter the name of the ACOB TIP library file. Do not enter a trailing period after the file name.

The default is `SYS$LIB$*ACOB-TIPLIB`.

File Containing ACOB CBEP\$

Enter the name of the file containing the COBOL Common Bank entry point table. Ensure that the CBEP\$ file you specify matches the COBOL compiler specified by you. Do not enter a trailing period after the file name.

The default is *SY\$LIB\$*ACOB-DML*.

ACOB Library

Enter the name of the ACOB library file. Do not enter a trailing period after the file name.

The default is *SY\$LIB\$*ACOB*.

TIP RUN\$ File

Enter the name of the TIP RUN\$ file. Do not enter a trailing period after the file name.

The default is *TIP\$*TIPRUN\$*.

TIP LIB\$ File (for MCB)

Enter the name of the TIP library file containing the MCB interface routines for the application group within which the OS 2200 based system runs. Do not enter a trailing period after the file name.

The TIP LIB\$ file contains the TIP primitive subroutines and the MCB interface routines. The MCB interface routines can be specific to each application group, depending on the method used when they were installed. Refer to the *TIP Installation Guide* for more information.

The default is *TIP\$*TIPLIB\$*.

File Containing CBEP\$\$MCB

Enter the file name containing the CBEP\$\$MCB relocatable element for the application group previously specified for this configure. Do not enter a trailing period after the file name.

The relocatable element CBEP\$\$MCB is used during the collection of an OS 2200 based system to identify the MCB Common Banks. The MCB Common Bank is different for each application group.

The default is *MCB3*MCB\$*.

UC UCS C Compiler

Enter the name of the UC C Compiler file, which is commonly named as SY\$LIB\$*UC. Do not enter a trailing period after the file name.

UC is required for the generation of the OLTP UCS server systems.

The default is **NONE**.

Processor File Names Screen 2

This subsection describes the fields in the Processor File Names Screen 2.

RSA Relational Syntax Analyzer

Enter the name of the RSA library file associated with the application group within which the OS 2200 based system runs. Do not enter a trailing period after the file name.

The default is *SYS\$LIB\$*RSA*.

RSA Extended Mode Interface

Enter the name of the RSA library file for the extended mode interface. Do not enter a trailing period after the file name.

This is no longer a separate file and it is included in the RSA file. If applicable, enter the same file name that you entered in the **RSA Relational Syntax Analyzer** field described earlier in this subsection.

RDMS Relational Data Manager

Enter the name of the RDMS library file associated with the application group within which the OS 2200 based system run. Do not enter a trailing period after the file name.

The default is *SYS\$LIB\$*RDMS*.

ASSEMBLER (@MASM)

Enter the name of the MASM processor file. Do not enter a trailing period after the file name.

The default is *SYS\$LIB\$*MASM*.

PDP Processor (@PDP)

Enter the name of the file containing the PDP processor. Do not enter a trailing period after the file name.

The default is *SYS\$LIB\$*PDP*.

DDP Relocatable File Name

Use this field to identify the file containing the DDP-PPC DCA relocatable elements. This is used to create the HUBDDP server program. Agile Business Suite can use the DDP-PPC DCA interface for Automatic Entries between hosts.

The default is *SYS\$LIB\$*DDP-PPC-1*. If you intend to use Automatic Entries between hosts, *SYS\$LIB\$*DDP-PPC-1* is the usual file name.

DDN Relocatable File Name

Enter the file containing the DDP-PPC TCP/IP relocatable elements. This value is used to create the HUBDDN program. Agile Business Suite can use the DDP-PPC TCP/IP interface for Automatic Entries between hosts.

The default is `SY$LIB$*DDP-PPC-4`. If you intend to use Automatic Entries between hosts, `SY$LIB$*DDP-PPC-4` is the usual file name.

LINK Program Linker

Enter the name of the LINK program linker. Do not enter a trailing period after the file name.

LINK is part of the operating system and is required in the Runtime build.

The default is `SY$LIB$*LINK`.

IRU Integrated Recovery Utility

Enter the name of the file containing the IRU processor. Do not enter a trailing period after the file name.

The default is `SY$LIB$*IRU`.

ARC File Name

Enter the name of the file containing the CBEP\$\$ARC relocatable if you require Automatic Recovery (ARC). ARC recovery is specifically for the Background Run. `SY$LIB$*ARC` is the usual name for the ARC file. If you do not require this feature, choose the default value, `*NONE*`.

If a file is specified in this field, the Background Run is built so that it registers with ARC for software component recovery. ARC restarts the Background Run if an error causes termination.

Common Bank Attributes Screen

Use this screen to change the parameters controlling the data structures in the LINC\$TABLES Common Bank.

These parameters control the data structures in the LINC\$TABLES Common Bank.

Note: *Generally, you do not have to change the default settings without specific instructions from your Unisys Support Center.*

Work Queue Size

Enter a value in the range 1 through 999. The default is 200.

A work queue entry is made in the tables Common Bank for some of the requests to the Background Run. The logic commands Sleep, Message, Accept, Run, and Stop generate work queue entries. The work queue must be big enough to hold all the requests that can be active or pending at any given time.

Number of Slots

Enter a value in the range 1 through 999. The default is *250*.

Data structures called slots exist in the LINC\$TABLES Common Bank. A slot is allocated for each request being serviced by the Background Run. A request could be a Sleep, Message, SendMessage, Accept, or Run logic command or a :RUN system command.

Number of Items in the Pool

Enter the default value *50* under normal circumstances.

The Pool is an area of memory used to hold database records. This field determines the number of database records that can be handled by the pool at any given time.

Pool Size

Enter the default value *10,000* under normal circumstances.

The Pool is an area of memory used to hold database records. This field defines the size of the Pool (in words).

Maximum Number of Systems

Enter a number in the range 1 through 999. The default is *64*.

This field contains the maximum number of Agile Business Suite Systems that you want to run simultaneously under the Runtime.

HUB Configuration Parameters Screens

Use the HUB Configuration Parameters screens to change the parameters controlling the data structures in the LINC\$HUB Common Bank. The LINC\$HUB Common Bank controls external Automatic Entries within multiple copies of Runtime that have the same BDI and HUB identifier.

The two HUB Configuration Parameter screens are described in the following subsections.

HUB Configuration Parameter Screen 1

This subsection describes the fields on the first HUB Configuration Parameter screens.

LINC\$HUB BDI

Enter the BDI of the HUB Common Bank to be used by the configuration set.

The default is *0404642*.

HUB Configuration Identifier

Enter the single-character identifier for the HUB Configuration to be used by the environment. This character is used to form the runid of the HUB Background Run controlling the configuration, as follows:

```
HUB identifier BR
```

Generally, there would be only one HUB configuration for each host, but others can be defined for testing purposes. In this case, you should also change the LINC\$HUB BDI value. You must also ensure that the single-character identifier is unique on all hosts.

The default is *A*.

HUB Configuration Parameter Screen 2

This subsection describes the fields in the second HUB Configuration Parameter screen:

Work Queue Size

Enter the HUB work queue size. Enter a value in the range 1 through 999.

The default is *200*.

A work queue entry is made for every Automatic Entry request made to the HUB Background Run. The work queue must be big enough to record all concurrent requests.

Number of Slots

Data structures called slots exist in the *LINC\$HUB* Common Bank. A slot is allocated for each Auto request being serviced by the HUB Background Run.

In the Number of Slots field , enter the number of slots that can be used. Typically, the number of slots should be approximately 25 percent more than the sum of the number of work queue items and the number of items in the pool.

Enter a value in the range 1 through 999. The default is *250*.

Number of Items in the Pool

The Pool is an area of memory used to hold the database records being transferred to another system by using an external Automatic Entry.

Use this field to determine the number of database records that can be transferred at any given time. Enter a value in the range 1 through 999.

The default is *200*.

Pool Size

The Pool size should be the product of the average size of database records being transferred by using and external Automatic Entry and the number of items in the Pool.

Use this field to define the size of the Pool (in words). Enter a value in the range 1 through 30,000.

The default is *10,000*.

Maximum Number of Systems

Use this field to specify the maximum number of systems that you want to run simultaneously under the HUB. Enter a number in the range 1 through 999.

The default is *64*.

Maximum Number of Hosts

Use this field to control the number of independent hosts that can be connected to the HUB at a given time.

The default is *35*.

Maximum Environments / Host

Use this field to control the maximum number of copies of Runtime that can be defined in the HUB configuration. Enter a number in the range 1 through 64.

The default is *4*.

Maximum No. of DDN Programs

Use this field to control the maximum number of DDN (DDP-PPC TCP/IP) service programs associated with the HUB Background Run. Enter a number in the range 1 through 64. Batch runs with the following runid will start to service requests.

identifier DN server

The default is *4*.

Maximum No. of DDP Programs

Use this field to control the maximum number of DDP (DDP-PPC DCA) service programs associated with the HUB Background Run. Enter a number in the range 1 through 64. Batch runs with the following runid will start to service requests.

identifier DP server

The default is *4*.

Service Program Capacity

Use this field to control the volume of requests each service program (DDN or DDP) can process before the HUB Background Run starts another service program to deal with the excess. The default is 64.

OLTP Configuration Parameters Screen

The OLTP Configuration Parameters screen contains the following fields:

- \$OLTP-TM2200 Qualifier
- \$APP-GROUP-ID

Use the OLTP-TM2200 Qualifier to enter the name of the qualifier for the OLTP-TM2200 installed product filenames.

Use APP-GROUP-ID to enter the name of the UDS resource manager application group. You require this entry to use the Two Phase Commit option with the system.

LRSS Configuration Parameters Screen

Use the LRSS Configuration Parameters screen to change the parameters controlling the Remote Subroutine Server (LRSS).

This subsection describes the fields on the LRSS Configuration Parameters screen.

LINC\$LRSS BDI

Enter the BDI of the LRSS gate bank that is used to provide access to the TSU Subsystem for communication between Developer clients and the host. This BDI must be specified as an Application Level Extended Mode BDI. Application Level Extended Mode BDIs begin with 02, whereas Basic Mode BDIs begin with 04.

The subsystem is installed by using MODE LRSS or MODE ALL at SOLAR install time.

The default is 0205464.

LRSS Configuration Identifier

Enter the single-character identifier for the LRSS configuration to be used. This parameter identifies the LRSS TSU name to be used by the Runtime, so that A represents the TSU Name LNCARS, B represents the TSU Name LNCBRS, and so on.

It is also used to form the runid of the TCP/IP server, as follows:

LNCidentifierRS

The default is A.

Considerations

- Generally, there would be only one LRSS configuration for each host, but you can nominate another for testing purposes. In this case, you should change the LINC\$LRSS BDI value. You must also ensure that the single-character LRSS configuration identifier is unique on all hosts.
- The configuration file is *TSUname*TSUname* and the element name is *CONFIG*. Therefore, if you enter *A* for the configuration identifier, the configuration file will be referenced by *LNCARS*LNCARS.CONFIG*. This file is catalogued automatically as part of the Runtime installation.

The LRSS installation process creates two dummy elements, *CONFIG* and *FILES/6009* in the reference file for reference and editing. The version (6009) is the port number specified in the configuration file. If you use another port number, you should also create a corresponding *FILES/port-number* element. In the *FILES/port-number* element you should specify, in the SGS format, the files to be searched for the Object Modules that you want to call.

- CPCOMM is the default communications handler that uses the BDI number *0205222*. However, you can choose to target an alternate CPCOMM by editing the *CONFIG* element and inserting the CPCOMM <BDI-number> SGS.
- The TSU must be defined in the CPCOMM. For example, with *A* as the configuration identifier:

```
.  
. LRSS TSU  
PROCESS,LNCARS TYPE,TSAM ;  
INTERNET-ADR,ia-name ;  
PASSWORD,LNCARSPWD
```

Where, *ia-name* is the name of the Internet address. It must match the *ia-name* given in the *INTERNET-ADR* statement. Refer to the *CP Comm Installation and Configuration Guide* for more information.

DG (Builder Server) Configuration Parameters Screen

Use the DG Configuration Parameters screen to change the parameters controlling the Builder Server.

This subsection describes the fields in the DG Configuration Parameters screen.

LINC\$DG BDI

Enter the BDI of the DG gate bank that is used to provide access to the TSU Subsystem for communication between Developer clients and the host. This BDI must be specified as an Application Level Extended Mode BDI. Application Level Extended Mode BDIs begin with *02*, whereas Basic Mode BDIs begin with *04*.

The default is *0201643*.

DG Configuration Identifier

A DG Configuration Identifier must be assigned to every Builder Server installed on a single OS 2200 host. The DG Configuration Identifier must be a single alphabetical character. Therefore, you can use any letter in the range A through Z. The default is A. The DG Configuration Identifier identifies the TSU Name to be used by the Runtime. The TSU Name is *DIR<DG Configuration Identifier>GN* and the TSU Password is *DIR<DG Configuration Identifier>PWD*.

Considerations

- After a DG Configuration Identifier is assigned to a Builder Server, it should not be assigned to another Builder Server. A DG Configuration Identifier can only be reused if the previous Builder Server, to which it was assigned to, is uninstalled. If a DG Configuration Identifier is reused and the previous Builder Server is not uninstalled, the previously installed Builder Server will fail during the installation of the new Builder Server.
- CPCOMM is the default communications handler that uses the BDI number 0205222. However, you can choose to target an alternate CPCOMM by editing the CONFIG element and inserting the *CPCOMM<BDI-number>SGS*.
- The TSU must be defined in the CPCOMM as follows:

```
.  
  . DIREXT GEN TSU  
  PROCESS,DIRAGN  TYPE,TSAM ;  
    INTERNET-ADR, ia-name ;  
    PASSWORD,DIRAGNPWD
```

Where, *ia-name* is the name of the Internet address. It must match the *ia-name* given in the INTERNET-ADR statement. Refer to the *CP Comm Installation and Configuration Guide* for more information.

- In CPCommOS, add the following to the DIR<x>GN PROCESS configuration statement to update a DG port with TLS:

```
SSL/TLS-SECURITY,<name of an SSL/TLS-security statement> ;  
SSL/TLS-SECURE-PORTS,<port-number>
```

Then, add this port number to DIRGEN\$<x>*DGUTIL\$.CONFIG

This is performed to configure the Host to use the TLS encryption for communication.

COMUS Run Parameters

This subsection contains information on COMUS run parameters that are requested for the following tasks:

- First Build of OS 2200 Based Software
- Subsequent Builds of OS 2200 Based Software

First Build of OS 2200 Based Software

For the first BUILD of OS 2200 based Software, the COMUS parameters listed in the following table are requested. See “Subsequent Builds of OS 2200 Based Software” if you want to set up some of the COMUS parameters.

Parameter	Suggested Value or Action
Project ID	<i>ABSBUILD</i>
Runid	<i>BLDABS</i>
Run options	Transmit a space
Run priority	Transmit a space
Tape equipment	For example, <i>VTS</i>
Tape assign options	<i>TF</i>
Generation type	TAPE/TAPE
Permanent SGSs	Transmit a space
Maximum runtime	9999
Maximum pages	99999

Note: *If more than one build of Runtime is currently running, the Project ID must not duplicate the name of an active build of Runtime.*

Subsequent Builds of OS 2200 Based Software

For each subsequent build of the OS 2200 based software, the following COMUS parameters are requested. See “First Build of OS 2200 Based Software” if you want to set up some of the COMUS parameters.

Parameter	Suggested Value
MASTER reel	Reel number of the Release tape or the previous BUILD output tape (see comments following the table).
NEWMASTER reel	Reel number of the output tape (see comments following the table).
Generation ID	<i>01, 02</i> , and so on. The generation ID is displayed on the sign-on line after the version value. Do not use the apostrophe character ('). Site specific. 12 characters.
Heading	Optional text for your reference.
Reason	Optional text for your reference.

Parameter	Suggested Value
New change number	Transmit a space. (If installing a Unisys-supplied CHG or site-local code, enter the change number.)
Type of generation	UPDATE.
Additional SGSs	Transmit a space.
Runtime name	Name as used for the Runtime name on the General Configuration Parameters screen.

Reel Numbers

The Master and Newmaster reel numbers have additional options, as follows:

r1/r2/r3 . . . , options, type, expiry, [RING/NORING]

Where:

options indicate standard tape assign options.

type is the equipment type.

expiry is the number of days from the current date.

Optionally, include RING or NORING to indicate whether the tape is to be loaded with or without a Write ring, respectively.

For example:

TAPE1/TAPE2, TF, U9S, 45, RING

Files Created by Agile Business Suite

This section contains the information on the files created by Agile Business Suite when

- Installing Runtime
- Configuring and generating systems

The following conventions are used in this section:

- The *runtime* parameter indicates the name of the Runtime.
- The *system* parameter indicates the name of the Agile Business Suite system, whether it is a generated system or a Unisys-supplied software (for example, ROC).

Files Created when Installing Runtime

The following files are created when installing Runtime:

```
runtime*UTIL$
runtime*OLIB$
runtime*OMLIB$
runtime*ALIB$
runtime*SA$
runtime*CODES
runtime*CLDLOG
runtime*GLOBALST
runtime*GLOBALSG
runtime*LINCELMS
runtime*LINC$GLADTR$
runtime*PERM$SGS
```

The PERM\$SGS file is created when Runtime is installed. The parameters in this file describe the system settings. You can add additional SGSs after them. Do not delete these SGSs.

The LINC\$GLADTR\$ file is created on all the OS 2200 based hosts, but is used primarily on the XTC systems.

RDMS Storage Areas

A number of RDMS storage areas are created that contain the RDMS tables listed in the following table:

Storage Area File Name	Table Name	Description
SA\$	CONFIG	COMUS details
	LSYS	Details of all the OS 2200 based systems in the current Runtime
	PIDRANGES	Ranges of valid PIDs
	SERVICES	OLTP Service Names
	STNDEFAULT	Initial station record information
SA\$RI	REPORTINFO	Active Reports
SA\$RII		Index for SA\$RI
SA\$RR	REPORTSRUN	Completed Reports used in recovery
SA\$SI	SECURINT	Development System Security Information
SA\$SII		Index for SA\$SI
SA\$SU	SECURITY	Security information
SA\$SUI		Index for SA\$SU
SA\$ACC	ACCEPTS	SA\$ACC

Storage Area File Name	Table Name	Description
SA\$ACCI		Index for SA\$ACC
SA\$APID	ACTIVEPIDS	Clears PIDs during background run recovery
BCAST\$	BCAST	Flags for recovery of AUTOs
BCAST\$PRO	BCAST_PRO	Critical point data for Reports

Note: The *BCAST* and *BCAST_PRO* tables are only created for shared application groups on the XTC hosts.

Special Printing Attributes

The following files are created as sample files that must be modified if you want to use special printing attributes:

```
L3R3*CODES
runtime*UTIL$.LNET
```

Files Created when Configuring and Generating a System

The following files are created when configuring and generating a system:

File	Description
<i>system</i> *SYS\$LIB.	System configuration information plus some ECL (for example, LINC\$CNTL, RDML\$EXT, and COPY\$ECL)
<i>system</i> *TRX\$SYM.	Ispec logic symbolics
<i>system</i> *TRX\$REL.	Ispec logic object modules
<i>system</i> *TRX\$ABS.	Ispec logic absolutes
<i>system</i> *SCR\$SYM.	Ispec Screen subprogram symbolics
<i>system</i> *SCR\$REL.	Ispec Screen subprogram object modules
<i>system</i> *GEN\$RUN.	System generation runstreams for BATCH processing, serial, or split runs
<i>system</i> *PDP\$LIB.	Common database access code
<i>system</i> *REP\$SYM.	Report symbolics (if Reports exist)
<i>system</i> *REP\$REL.	Report object modules (if Reports exist)
<i>system</i> *REP\$ABS.	Report absolutes (if Reports exist)
<i>system</i> *REP\$RUN.	Report runstreams (if Reports exist)
<i>system</i> *STG\$REL	Report object modules (if Reports staged)

File	Description
<code>system*STG\$ABS</code>	Report absolutes (if Reports staged)
<code>system*STG\$RUN</code>	Report runstreams (if Reports staged)
<code>runtime*systemP\$.</code>	HVTIP library containing subprogram banks (ICP and Ispecs) of the system. For the UCS Subsystems, it is a SUPUR library containing the standard TIP ICP used to access the Subsystem.
<code>system*TRX\$SSDP.</code>	UCS Subsystem definition registered with the operating system during SOLAR PROLD. Exclusively assigned to the Exec until the Subsystem is deactivated. (It is not created for the HVTIP systems).
<code>runtime*systemS\$.</code>	Subsystem library of object modules. Exclusively assigned to the Exec until the Subsystem is deactivated. (It is not created for HVTIP systems).

Note: The `runtime*systemP$.` file is only valid if you are not using the HVTIP shared libraries. If the default duplex pack is specified, then the HVTIP library will be duplexed and the file will be `runtime*system$2P$.`

Output from Configure or Generate

The P\$ file is cycled, enabling you to access previous runs. Each Report Batch generate and Individual Report generates use one cycle of the P\$ file.

If you choose to split runs for the generate or configure, the following files are created:

- For compile phase:
`system*P$CMPn.`
- For linking phase:
`system*P$MAPn.`

Where, n range from 2 to the number of splits specified.

Database Files

The following database files are created when configuring or generating a system:

```
database*databaseispec.  
database*$tipispec. :TIP Ispec leg 2  
database*P$TIPtip. :TIP Profile leg 1  
database*P$2TIPtip. :TIP Profile leg 2  
database*profile.  
database*databaseC_R_I.  
database*$tipC_R_I. :TIP Duplex  
database*databaseD_A_D.
```

```
database*$tipD_A_D. :TIP Duplex
database*databaseH_U_B.
database*$tipH_U_B. :TIP Duplex
database*databaseL-TRC.
database*$tipL-TRC. :TIP Duplex
database*databaseS_T_N.
database*$tipS_T_N. :TIP Duplex
```

Where:

- *tip* is the TIP number. Valid length for the TIP number is six digits. (for example, 000230).
- *database* is the name of your database.
- *ispec* is an Ispec name.
- *profile* is a Profile name.

Appendix A

Installing Interim Corrections

An Agile Business Suite Interim Correction (IC) is a software package that is designed to distribute fixes and updates for the General Customer Availability (GCA) version of the Development Environment, Client Environment, and Runtime.

If the GCA version of the Development Environment and Runtime is not detected, Browse to GCA path dialog box appears. You can browse to the Development Environment subfolder (or the equivalent Windows Runtime subfolder for a Runtime installation) in the AB Suite installer and follow the wizard instructions. The IC can then be installed using the license provided in the GCA, without actually installing the GCA version. This allows clean installs of an IC without having to install old versions of the product first.

For the MCP Runtime, the following message appears, if you try to install the Runtime from an IC and the GCA release is not detected. For information on installing an IC for MCP Runtime, see [Installing Interim Corrections for Runtime for ClearPath MCP](#).

```
>>> (<usercode>)NGEN30/AUTHENTICATE ON <pack> IS MISSING OR INVALID <<<  
COPY VALID AUTHENTICATE FILE FROM THE GCA RELEASE: AX TO CONTINUE OR DS
```

Note: You can directly install an IC release on a clean machine without the GCA version being installed. If there is no GCA version installed, the IC runs as a new base installation.

Interim Corrections are distributed on the support web site for the product at:

<https://www.support.unisys.com/common/ShowWebPage.aspx?id=1046&pla=ABS&nav=ABS>

They are available as zip files for download. Once you have downloaded and saved the appropriate Interim Correction file, to a temporary location, to update your installed application, perform the following:

1. Extract the contents of the zip file to a temporary location.
2. Locate the CD Developer folder and run the CD Browser.exe to begin the installation.

The IC Install program performs the following checks:

- Check that an existing copy of Agile Business Suite Developer or Agile Business Suite Runtime GCA version is installed.
 - Check if files which need to be updated are in use.
3. If the checks are successful, a dialog box appears which confirms that an existing version of the software exists. The existing version is upgraded prior to continuing with the installation of the IC.
 4. Click **Yes** to continue, or **Cancel** to exit the installation.

5. If Agile Business Suite Runtime environment is also installed on the same computer as Developer, the IC for Developer changes the version numbers between the two products. Therefore you must upgrade the Runtime environment to the equivalent version after you have completed the Developer upgrade. A dialog box advises you of this requirement, and asks you to confirm that you wish to continue with the Developer upgrade.
6. Click **Yes** to continue, or **No** to exit the installation.

From this point, the installation proceeds in the same way as the base GCA release installation. Refer to Performing the Developer Installation for more information.

Installing Interim Corrections for Runtime for ClearPath MCP

Copying the Runtime Install Job from the Release Media

To copy the MCP Runtime install job from the release media, perform the following:

1. Obtain the release media and extract the IC container from its zip file to a temporary location.
2. Map a network drive to your privileged usercode on the MCP host.
3. Copy the container file to the MCP host.
4. Disconnect the network drive.
5. From CANDE, log in using the privileged usercode and unwrap the container file.

```
WFL UNWRAP *= OUTOF <container file>  
TO <Transfer pack> (RESTRICTED=FALSE)
```

6. Download the installation WFL.

```
COPY (TRANSFER) IC/90/<IC number>/NGEN30/WFL/RUNTIME  
AS NGEN30/WFL/RUNTIME  
FROM <Transfer pack> (PACK)
```

Installing the Authenticate File

The Authenticate file allows you to install an IC release to a new runtime environment without installing the GCA release first. Install the Authenticate file if you are installing an IC release to a new runtime environment.

To install the authentication file, run the following command:

```
WFL UNWRAP (TRANSFER) GCA/90/1000-<nn>/NGEN30/AUTHENTICATE  
AS (<Runtime Usercode>) NGEN30/AUTHENTICATE  
OUTOF <GCA container>  
TO <Runtime pack> (RESTRICTED=FALSE)
```

Installing the MCP Runtime Software

To install the MCP Runtime software, perform the following:

1. Log in with privileged usercode.
2. Start the Runtime WFL by entering:

```
START NGEN30/WFL/RUNTIME
("usercode", "pack", "aliaspack", media parameter)
```

The *usercode* value is the usercode to which the Runtime is installed, which might be an asterisk (*).

The *pack* value is the family name of the pack to which the Runtime is installed, which might be *DISK* or *altpack*.

The *aliaspack* value is the pack for your station alias file. Refer to the *Agile Business Suite Runtime for ClearPath MCP Administration Guide* for more information on station aliases.

media parameter = "MD=*MediaDirectory* MN=*MediaName* N=*Release#*"

MediaDirectory is the directory containing the installation files:

(TRANSFER)IC

MediaName is the name of the pack on which the installation files are located.

<Transfer pack>

Release# is the number from the release container file and has the format **nnnn-nn**.

<IC number>

For example:

```
START NGEN30/WFL/RUNTIME
("RTUSER", "RTPACK", "DISK",
"MD=(TRANSFER)ETA/IC MN=TFRPACK N=1001-01")
```

If the installation does not detect GCA release, you will be prompted with the following messages.

```
>>> (<usercode>)NGEN30/AUTHENTICATE ON <pack> IS MISSING OR INVALID <<<
COPY VALID AUTHENTICATE FILE FROM THE GCA RELEASE: AX TO CONTINUE OR DS
```

When the messages appear, perform the following:

1. Copy the valid authenticate file from the GCA release to (<usercode>)/NGEN30/AUTHENTICATE ON <pack> and respond with AX to continue with the installation.

Refer to [Installing the Authenticate File](#) for instructions on retrieving the authenticate file.

2. Respond with DS to terminate the installation.

Note: These messages cannot be translated because `MLSLIBRARY` has not been installed yet.

Performing the First Application Build after Updating the Runtime

To improve application availability during the first deployment after an AB Suite IC update, the MCP Runtime deployment process has been enhanced to limit the occasions when an active application must be disabled for the duration of the first system deployment after an IC update.

For most IC updates, it is possible for the application to remain active during the first deployment after the IC update. After installing an IC for the MCP Runtime (and the associated Developer release), you can leave your application active while you do the next system build.

However, it is still necessary to use the Rebuild option with the first deployment of the system and reports after an IC update, and you must deploy all reports. This ensures code consistency across the application.

There are instances when it is necessary to have the system disabled for the duration of the first deployment, or to restart the system after the first deployment. The conditions that require the system to be disabled for the first deployment or to be restarted after the first deployment are described below.

Application Build Instructions

To deploy your application, perform the following steps:

1. As a part of pre-build preparation, remove your BuilderCache and BuilderOutput directories.
2. Start the deployment.
 - a. Right-click the deployment folder and select **Rebuild** or **Folder Only Rebuild**.
 - b. On the **Host Login** dialog box enter the login details.
 - c. Click **OK**.
3. Respond to prompts and Build Log messages as recommended in the following topics.

LINCSUPPORT

If there is a change to LINCSUPPORT, the system must be disabled for the duration of the first deployment. This prevents duplicate LINCSUPPORT libraries in the mix for the application, which causes the system to hang.

After an IC has been installed, the first system deployment will check for a change to LINC SUPPORT and check whether the application is active. If there is a change to LINC SUPPORT and the application is active, the deployment will advise the user that the application must be disabled for the duration of the rest of the deployment. The deployment will not continue until the application has been disabled.

The following messages appear in the Build Log for a build or the Sumlog for a transfer:

```
"New LINC SUPPORT installed, you must disable your system to continue the deployment."
```

```
"PROGRAMMATICALLY SUSPENDED"
```

```
"<database> CONTROL FILE IN USE - WHEN DB CLOSED, OK TO CONTINUE"
```

Action required:

1. Disable the system.
2. Respond to the waiting entry.

ENVIRONMENT, LSS, and COMS_LINC_TP

The application might be active during the first deployment after the IC update. If there is a change to ENVIRONMENT, LSS, or COMSP_LINC_TP, the system must be restarted after the deployment. This activates the newly installed code files for these libraries.

After an IC has been installed, the first system deployment will check for a change to ENVIRONMENT, LSS, and COMS_LINC_TP and check whether the application is active. If there is a change to any of these libraries and the application is active, the deployment will include a log entry in the log for each of the changed libraries. (For builds, the message will be included in the Build Log. For transfers, the message will be in the Sumlog.) The log entry will advise the user that the application must be restarted after the deployment is complete.

The following messages might appear in the Build Log for a build or the Sumlog for a transfer.

```
"New LSS installed, RESTART application after this generate Job <job#>"
```

```
"New COMSTP installed, RESTART application after this generate Job <job#>"
```

```
"New ENVIRONMENT installed, RESTART application after this generate Job <job#>"
```

Action required:

1. Wait for the deployment to complete.
2. Restart the system immediately.

Recommendation:

If you choose to allow your application to remain active during the first deployment after an IC update and you do not normally review the Build Log or Sumlog afterwards, you should always restart your application after first deployment to ensure that the new libraries are activated.

LOGIC

If there is a change to LOGIC, the first system deployment after installing the IC must be a build with the Rebuild option. Having some code libraries with the old LOGIC and some code libraries with the new LOGIC would result in runtime issues.

After an IC is installed, the first system deployment checks for a change to LOGIC and then checks whether the deployment is using the Build or Rebuild option. If there is a change to LOGIC and the deployment is using the Build option, a message is logged in the Build Log. The message advises you to deploy your application with the Rebuild option. You must do this as soon as possible after the deployment is complete.

The following message appears in the Build Log:

```
"A new LOGIC is available. The application should be deployed with a REBUILD."
```

Action required:

1. Wait for the deployment to complete.
2. Deploy the system with the Rebuild option.

Recommendation:

The first system deployment after an IC update must be a build with the Rebuild option. This applies to the source system used in Runtime Transfers as well.

If you are performing the first deployment of the source system for the Runtime Transfer after an IC update and you see a message in the Build log, you must do another deployment with the Rebuild option before you perform the transfer to deploy the target system.

REPORT_INFO

If there is a change to REPORT_INFO, the first report deployment after installing the IC must include all reports. (If it is not possible to deploy all the reports at once, deploy the critical online reports first, and then the batch reports.)

After an IC is installed, the first report deployment checks for a change to REPORT_INFO and then checks whether the report deployment is using the Rebuild option. If there is a change to REPORT_INFO and the report deployment is not a Rebuild, a message is logged in the Build Log. The message inform you that REPORT_INFO has changed.

The following message appears in the Build Log.

```
"New REPORT DUMPINFO is available, all reports require a REBUILD"
```

Action required:

1. Wait for the deployment to complete.
2. Deploy all reports with the Rebuild option.

Recommendation:

The first report deployment after an IC update must be a build with the Rebuild option. This applies to the source application used in Runtime Transfers as well.

If you are performing the first deployment of the source application for the Runtime Transfer after an IC update and you see the message in the Build log, you must perform another deployment with the Rebuild option before you perform the transfer to deploy the target system.

If you see the message in the Build log and have included all the reports within a system build, perform another report build with the Rebuild option only if the last report build was done with the Build option.

Appendix B

Creating and Configuring User Accounts Using the AB Ready Tool

You can also use the AB Ready Tool to create and configure the user accounts (Application Users and Application Administrative Users).

To create and configure the user accounts using the AB Ready Tool:

1. In the AB Suite installer folder, navigate to **CD Developer\ABReady**.
2. Run the **AB Ready Tool** application.
3. In the **Welcome to AB Ready Tool** screen, select **Create/Configure User Accounts**.



104066

4. In the **Create/Configure User Accounts** screen, you can perform three tasks.
 - Configure the existing Application Users and Application Administration Users.
 - Create and configure new Application Users and Application Administration Users manually.

Creating and Configuring User Accounts Using the AB Ready Tool

- Create and configure new Application Users and Application Administration Users automatically.



Configuring Existing AB Suite Service Accounts

For configuring existing Application Users and Application Administration Users in the Configure Existing AB Suite Service Accounts screen:

1. Enter the **Domain** and **User Name**; or enter the **Domain**, click **List Users**, and select the user in the list box.
2. Select **Qualify Account for Application User** or **Qualify Account for Application Administrative User**.

Creating and Configuring User Accounts Using the AB Ready Tool

Configure Existing AB Suite Service Accounts

1. Please enter the domain for your Application User and Application Administrative User accounts.

Domain :

2. Please enter the User Name or select an User Account to qualify

User Name :

NFR1000

NFR101

NFR102

NFR103

3. Click on either Qualify Account for Application User or Qualify Account for Application Administrative User.

Qualify Account for Application User

Qualify Account for Application Administrative User

104086

3. Enter the password and click **OK** to qualify the user account.

Configure Existing AB Suite Service Accounts

1. Please enter the domain for your Application User and Application Administrative User accounts.

Domain :

2. Please enter the User Name or select an User Account to qualify

User Name :

NFR1000

NFR101

NFR102

NFR103

3. Click on either (Qualify Account for Application User or Qualify Account for Application Administrative User.

Qualify Account for Application User

Qualify Account for Application Administrative User


104087

Creating and Configuring New AB Suite Service Accounts Manually

To create and configure new Application Users and Application Administration Users manually in the **Create and Configure New AB Suite Service Accounts** screen:

Creating and Configuring User Accounts Using the AB Ready Tool

1. Select the user account you want to create.



104088

2. In the next screen, enter the **Domain**, **User Name**, and **Password**; and select **Create and Configure** to complete the user account creation and configuration process.

Creating and Configuring User Accounts Using the AB Ready Tool

Create Application User Accounts



AB Suite® 8.0

© 2021 Unisys Corporation.
All rights reserved.

Create Application User Accounts

Enter the new user details and AB Ready will attempt to create the user and configure it for use as an Application User Account.

Domain

User Name

Password

Confirm Password

[Create and Configure](#)

104089

Create Application Administrative User Accounts



AB Suite® 8.0

© 2021 Unisys Corporation.
All rights reserved.

Create Application Administrative User Accounts

Enter the new user details and AB Ready will attempt to create the user and configure it for use as an Application Administrative User Account.

Domain

User Name

Password


Confirm Password

[Create and Configure](#)

104090

Creating and Configuring New AB Suite Service Accounts Automatically

To create and configure new Application Users and Application Administration Users automatically in the **Create and Configure AB Suite User Accounts** screen, select the **AB Suite Version** and select **Create and Configure** to complete the user account creation and configuration process.



Create and Configure AB Suite User Accounts

Automatically Create new AB Suite User Accounts

AB Suite® 8.0

AB Suite: Version

Please select AB Suite version.

[Create and Configure](#)

© 2021 Unisys Corporation.
All rights reserved.

< Back Exit

104091

